
cloud-init

Release 22.4.2

unknown

Nov 23, 2022

GETTING STARTED

1	Project and community	3
2	Having trouble? We would like to help!	5
2.1	Tutorial	5
2.2	Availability	7
2.3	Boot Stages	9
2.4	CLI Interface	12
2.5	FAQ	17
2.6	Reporting Bugs	24
2.7	Configuration Sources	25
2.8	User-Data Formats	26
2.9	Cloud config examples	30
2.10	Events and Updates	66
2.11	Merging User-Data Sections	68
2.12	Instance Metadata	72
2.13	Datasources	85
2.14	Vendor Data	118
2.15	Network Configuration	119
2.16	Base Configuration	144
2.17	Module Reference	149
2.18	Contributing to cloud-init	220
2.19	Module Creation	224
2.20	Code Review Process	226
2.21	Security	230
2.22	Debugging cloud-init	231
2.23	Logging	235
2.24	Directory layout	239
2.25	Analyze	240
2.26	Docs	245
2.27	Testing	247
2.28	Integration Testing	249
	Python Module Index	253
	Index	255

Cloud-init is the *industry standard* multi-distribution method for cross-platform cloud instance initialization.

During boot, cloud-init identifies the cloud it is running on and initializes the system accordingly. Cloud instances will automatically be provisioned during first boot with networking, storage, ssh keys, packages and various other system aspects already configured.

Cloud-init provides the necessary glue between launching a cloud instance and connecting to it so that it works as expected.

For cloud users, cloud-init provides no-install first-boot configuration management of a cloud instance. For cloud providers, it provides instance setup that can be integrated with your cloud.

PROJECT AND COMMUNITY

Cloud-init is an open source project that warmly welcomes community projects, contributions, suggestions, fixes and constructive feedback.

- [Code of conduct](#)
- Ask questions in IRC on `#cloud-init` on Libera
- [Mailing list](#)
- [Contribute on Github](#)
- [Release schedule](#)

HAVING TROUBLE? WE WOULD LIKE TO HELP!

- Check out the [Tutorial](#) if you're new to cloud-init
- Try the [FAQ](#) for answers to some common questions
- Find a bug? [Report bugs on Launchpad](#)

2.1 Tutorial

In this tutorial, we will create our first cloud-init user data script and deploy it into an LXD container. We'll be using [LXD](#) for this tutorial because it provides first class support for cloud-init user data as well as systemd support. Because it is container based, it allows for quick testing and iterating on our user data definition.

2.1.1 Setup LXD

Skip this section if you already have [LXD](#) setup.

Install LXD

```
$ sudo snap install lxd
```

If you don't have snap, you can install LXD using one of the [other installation options](#).

Initialize LXD

```
$ lxd init --minimal
```

The minimal configuration should work fine for our purposes. It can always be changed at a later time if needed.

2.1.2 Define our user data

Now that LXD is setup, we can define our user data. Create the following file on your local filesystem at `/tmp/my-user-data`:

```
#cloud-config
runcmd:
- echo 'Hello, World!' > /var/tmp/hello-world.txt
```

Here we are defining our cloud-init user data in the *cloud-config* format, using the *runcmd* module to define a command to run. When applied, it should write `Hello, World!` to `/var/tmp/hello-world.txt`.

2.1.3 Launch a container with our user data

Now that we have LXD setup and our user data defined, we can launch an instance with our user data:

```
$ lxc launch ubuntu:focal my-test --config=user.user-data="$(cat /tmp/my-user-data)"
```

2.1.4 Verify that cloud-init ran successfully

After launching the container, we should be able to connect to our instance using

```
$ lxc shell my-test
```

You should now be in a shell inside the LXD instance. Before validating the user data, let's wait for cloud-init to complete successfully:

```
$ cloud-init status --wait
.....
cloud-init status: done
$
```

We can now verify that cloud-init received the expected user data:

```
$ cloud-init query userdata
#cloud-config
runcmd:
- echo 'Hello, World!' > /var/tmp/hello-world.txt
```

We can also assert the user data we provided is a valid cloud-config:

```
$ cloud-init schema --system --annotate
Valid cloud-config: system userdata
$
```

Finally, verify that our user data was applied successfully:

```
$ cat /var/tmp/hello-world.txt
Hello, World!
$
```

We can see that cloud-init has consumed our user data successfully!

2.1.5 Tear down

Exit the container shell (i.e., using `exit` or `ctrl-d`). Once we have exited the container, we can stop the container using:

```
$ lxc stop my-test
```

and we can remove the container using:

```
$ lxc rm my-test
```

2.1.6 What's next?

In this tutorial, we used the `runcmd` module to execute a shell command. The full list of modules available can be found in [modules documentation](#). Each module contains examples of how to use it.

You can also head over to the [examples](#) page for examples of more common use cases.

2.2 Availability

Below outlines the current availability of cloud-init across distributions and clouds, both public and private.

Note: If a distribution or cloud does not show up in the list below contact them and ask for images to be generated using cloud-init!

2.2.1 Distributions

Cloud-init has support across all major Linux distributions, FreeBSD, NetBSD, OpenBSD and DragonFlyBSD:

- Alpine Linux
- Arch Linux
- Debian
- DragonFlyBSD
- Fedora
- FreeBSD
- Gentoo Linux
- NetBSD
- OpenBSD
- Photon OS
- RHEL/CentOS/AlmaLinux/Rocky Linux/EuroLinux
- SLES/openSUSE
- Ubuntu

2.2.2 Clouds

Cloud-init provides support across a wide ranging list of execution environments in the public cloud:

- Amazon Web Services
- Microsoft Azure
- Google Cloud Platform
- Oracle Cloud Infrastructure
- Softlayer
- Rackspace Public Cloud
- IBM Cloud
- DigitalOcean
- Bigstep
- Hetzner
- Joyent
- CloudSigma
- Alibaba Cloud
- OVH
- OpenNebula
- Exoscale
- Scaleway
- CloudStack
- AltCloud
- SmartOS
- UpCloud
- Vultr
- Zadara Edge Cloud Platform
- 3DS Outscale

Additionally, cloud-init is supported on these private clouds:

- Bare metal installs
- OpenStack
- LXD
- KVM
- Metal-as-a-Service (MAAS)
- VMware

2.3 Boot Stages

In order to be able to provide the functionality that it does, cloud-init must be integrated into the boot in fairly controlled way. There are five stages to boot:

1. Generator
2. Local
3. Network
4. Config
5. Final

2.3.1 Generator

When booting under systemd, a [generator](#) will run that determines if cloud-init.target should be included in the boot goals. By default, this generator will enable cloud-init. It will not enable cloud-init if either:

- The file `/etc/cloud/cloud-init.disabled` exists
- The kernel command line as found in `/proc/cmdline` contains `cloud-init=disabled`. When running in a container, the kernel command line is not honored, but cloud-init will read an environment variable named `KERNEL_CMDLINE` in its place.

Again, these mechanisms for disabling cloud-init at runtime currently only exist in systemd.

2.3.2 Local

systemd service	cloud-init-local.service
runs	as soon as possible with / mounted read-write
blocks	as much of boot as possible, <i>must</i> block network
modules	none

The purpose of the local stage is to:

- locate “local” data sources.
- apply networking configuration to the system (including “Fallback”)

In most cases, this stage does not do much more than that. It finds the datasource and determines the network configuration to be used. That network configuration can come from:

- **datasource**: cloud provided network configuration via metadata
- **fallback**: cloud-init’s fallback networking consists of rendering the equivalent to “dhcp on eth0”, which was historically the most popular mechanism for network configuration of a guest
- **none**: network configuration can be disabled by writing the file `/etc/cloud/cloud.cfg` with the content:
`network: {config: disabled}`

If this is an instance’s first boot, then the selected network configuration is rendered. This includes clearing of all previous (stale) configuration including persistent device naming with old mac addresses.

This stage must block network bring-up or any stale configuration that might have already been applied. Otherwise, that could have negative effects such as DHCP hooks or broadcast of an old hostname. It would also put the system in an odd state to recover from, as it may then have to restart network devices.

Cloud-init then exits and expects for the continued boot of the operating system to bring network configuration up as configured.

Note: In the past, local data sources have been only those that were available without network (such as ‘ConfigDrive’). However, as seen in the recent additions to the DigitalOcean datasource, even data sources that require a network can operate at this stage.

2.3.3 Network

systemd service	<code>cloud-init.service</code>
runs	after local stage and configured networking is up
blocks	as much of remaining boot as possible
modules	<code>cloud_init_modules</code> in <code>/etc/cloud/cloud.cfg</code>

This stage requires all configured networking to be online, as it will fully process any user-data that is found. Here processing means:

- retrieve any `#include` or `#include-once` (recursively) including http
- decompress any compressed content
- run any part-handler found.

This stage runs the `disk_setup` and `mounts` modules which may partition and format disks and configure mount points (such as in `/etc/fstab`). Those modules cannot run earlier as they may receive configuration input from sources only available via network. For example, a user may have provided user-data in a network resource that describes how local mounts should be done.

On some clouds, such as Azure, this stage will create filesystems to be mounted, including ones that have stale (previous instance) references in `/etc/fstab`. As such, entries `/etc/fstab` other than those necessary for cloud-init to run should not be done until after this stage.

A part-handler will run at this stage, as will boot-hooks including cloud-config `bootcmd`. The user of this functionality has to be aware that the system is in the process of booting when their code runs.

2.3.4 Config

systemd service	<code>cloud-config.service</code>
runs	after network
blocks	nothing
modules	<code>cloud_config_modules</code> in <code>/etc/cloud/cloud.cfg</code>

This stage runs config modules only. Modules that do not really have an effect on other stages of boot are run here, including `runcmd`.

2.3.5 Final

systemd service	<code>cloud-final.service</code>
runs	as final part of boot (traditional “rc.local”)
blocks	nothing
modules	<code>cloud_final_modules</code> in <code>/etc/cloud/cloud.cfg</code>

This stage runs as late in boot as possible. Any scripts that a user is accustomed to running after logging into a system should run correctly here. Things that run here include:

- package installations
- configuration management plugins (ansible, puppet, chef, salt-minion)
- user-defined scripts (i.e. shell scripts passed as user-data)

For scripts external to cloud-init looking to wait until cloud-init is finished, the `cloud-init status --wait` sub-command can help block external scripts until cloud-init is done without having to write your own systemd units dependency chains. See [status](#) for more info.

2.3.6 First Boot Determination

cloud-init has to determine whether or not the current boot is the first boot of a new instance or not, so that it applies the appropriate configuration. On an instance’s first boot, it should run all “per-instance” configuration, whereas on a subsequent boot it should run only “per-boot” configuration. This section describes how cloud-init performs this determination, as well as why it is necessary.

When it runs, cloud-init stores a cache of its internal state for use across stages and boots.

If this cache is present, then cloud-init has run on this system before.¹ There are two cases where this could occur. Most commonly, the instance has been rebooted, and this is a second/subsequent boot. Alternatively, the filesystem has been attached to a *new* instance, and this is an instance’s first boot. The most obvious case where this happens is when an instance is launched from an image captured from a launched instance.

By default, cloud-init attempts to determine which case it is running in by checking the instance ID in the cache against the instance ID it determines at runtime. If they do not match, then this is an instance’s first boot; otherwise, it’s a subsequent boot. Internally, cloud-init refers to this behavior as `check`.

This behavior is required for images captured from launched instances to behave correctly, and so is the default which generic cloud images ship with. However, there are cases where it can cause problems.² For these cases, cloud-init has support for modifying its behavior to trust the instance ID that is present in the system unconditionally. This means that cloud-init will never detect a new instance when the cache is present, and it follows that the only way to cause cloud-init to detect a new instance (and therefore its first boot) is to manually remove cloud-init’s cache. Internally, this behavior is referred to as `trust`.

To configure which of these behaviors to use, cloud-init exposes the `manual_cache_clean` configuration option. When `false` (the default), cloud-init will `check` and clean the cache if the instance IDs do not match (this is the default, as discussed above). When `true`, cloud-init will `trust` the existing cache (and therefore not clean it).

¹ It follows that if this cache is not present, cloud-init has not run on this system before, so this is unambiguously this instance’s first boot.

² A couple of ways in which this strict reliance on the presence of a datasource has been observed to cause problems:

- If a cloud’s metadata service is flaky and cloud-init cannot obtain the instance ID locally on that platform, cloud-init’s instance ID determination will sometimes fail to determine the current instance ID, which makes it impossible to determine if this is an instance’s first or subsequent boot (#1885527).
- If cloud-init is used to provision a physical appliance or device and an attacker can present a datasource to the device with a different instance ID, then cloud-init’s default behavior will detect this as an instance’s first boot and reset the device using the attacker’s configuration (this has been observed with the NoCloud datasource in #1879530).

2.3.7 Manual Cache Cleaning

cloud-init ships a command for manually cleaning the cache: `cloud-init clean`. See *clean*'s documentation for further details.

2.3.8 Reverting `manual_cache_clean` Setting

Currently there is no support for switching an instance that is launched with `manual_cache_clean: true` from trust behavior to check behavior, other than manually cleaning the cache.

Warning: If you want to capture an instance that is currently in trust mode as an image for launching other instances, you **must** manually clean the cache. If you do not do so, then instances launched from the captured image will all detect their first boot as a subsequent boot of the captured instance, and will not apply any per-instance configuration.

This is a functional issue, but also a potential security one: cloud-init is responsible for rotating SSH host keys on first boot, and this will not happen on these instances.

2.4 CLI Interface

For the latest list of subcommands and arguments use cloud-init's `--help` option. This can be used against cloud-init itself or any of its subcommands.

```
$ cloud-init --help
usage: cloud-init [-h] [--version] [--file FILES] [--debug] [--force]
                  {init,modules,single,query,
↳ dhclient-hook,features,analyze,devel,collect-logs,clean,status,schema} ...

options:
  -h, --help            show this help message and exit
  --version, -v          Show program's version number and exit.
  --file FILES, -f FILES
                        Use additional yaml configuration files.
  --debug, -d           Show additional pre-action logging (default: False).
  --force               Force running even if no datasource is found (use at your own
↳ risk).

Subcommands:
  {init,modules,single,query,dhclient-hook,features,analyze,devel,collect-logs,clean,
↳ status,schema}
  init                  Initialize cloud-init and perform initial modules.
  modules               Activate modules using a given configuration key.
  single                Run a single module.
  query                 Query standardized instance metadata from the command line.
  dhclient-hook         Run the dhclient hook to record network info.
  features              List defined features.
  analyze               Devel tool: Analyze cloud-init logs and data.
  devel                 Run development tools.
  collect-logs          Collect and tar all cloud-init debug info.
  clean                 Remove logs and artifacts so cloud-init can re-run.
```

(continues on next page)

(continued from previous page)

status	Report cloud-init status or wait on completion.
schema	Validate cloud-config files using jsonschema.

The rest of this document will give an overview of each of the subcommands.

2.4.1 analyze

Get detailed reports of where cloud-init spends its time during the boot process. For more complete reference see [Analyze](#).

Possible subcommands include:

- *blame*: report ordered by most costly operations
- *dump*: machine-readable JSON dump of all cloud-init tracked events
- *show*: show time-ordered report of the cost of operations during each boot stage
- *boot*: show timestamps from kernel initialization, kernel finish initialization, and cloud-init start

2.4.2 clean

Remove cloud-init artifacts from `/var/lib/cloud` to simulate a clean instance. On reboot, cloud-init will re-run all stages as it did on first boot.

- `--logs`: optionally remove all cloud-init log files in `/var/log/`
- `--reboot`: reboot the system after removing artifacts
- `--machine-id`: Remove `/etc/machine-id` on this image. Best practice when cloning a golden image to ensure that the next boot of that image auto-generates an unique machine ID. [More details on machine-id](#).

2.4.3 collect-logs

Collect and tar cloud-init generated logs, data files, and system information for triage. This subcommand is integrated with `apport`.

Logs collected include:

- `/var/log/cloud-init.log`
- `/var/log/cloud-init-output.log`
- `/run/cloud-init`
- `/var/lib/cloud/instance/user-data.txt`
- cloud-init package version
- `dmesg` output
- `journalctl` output

Note: Ubuntu users can file bugs with `ubuntu-bug cloud-init` to automatically attach these logs to a bug report

2.4.4 devel

Collection of development tools under active development. These tools will likely be promoted to top-level subcommands when stable.

Do **NOT** rely on the output of these commands as they can and will change.

Current subcommands:

- **net-convert**: manually use cloud-init's network format conversion, useful for testing configuration or testing changes to the network conversion logic itself.
- **render**: use cloud-init's jinja template render to process **#cloud-config** or **custom-scripts**, injecting any variables from `/run/cloud-init/instance-data.json`. It accepts a user-data file containing the jinja template header `## template: jinja` and renders that content with any instance-data.json variables present.
- **hotplug-hook**: respond to newly added system devices by retrieving updated system metadata and bringing up/down the corresponding device. This command is intended to be called via a systemd service and is not considered user-accessible except for debugging purposes.

2.4.5 features

Print out each feature supported. If cloud-init does not have the features subcommand, it also does not support any features described in this document.

```
$ cloud-init features
NETWORK_CONFIG_V1
NETWORK_CONFIG_V2
```

2.4.6 init

Generally run by OS init systems to execute cloud-init's stages *init* and *init-local*. See [Boot Stages](#) for more info. Can be run on the commandline, but is generally gated to run only once due to semaphores in `/var/lib/cloud/instance/sem/` and `/var/lib/cloud/sem`.

- `--local`: run *init-local* stage instead of *init*

2.4.7 modules

Generally run by OS init systems to execute *modules:config* and *modules:final* boot stages. This executes cloud config [Module Reference](#) configured to run in the init, config and final stages. The modules are declared to run in various boot stages in the file `/etc/cloud/cloud.cfg` under keys:

- *cloud_init_modules*
- *cloud_config_modules*
- *cloud_final_modules*

Can be run on the command line, but each module is gated to run only once due to semaphores in `/var/lib/cloud/`.

- `--mode [init|config|final]`: run *modules:init*, *modules:config* or *modules:final* cloud-init stages. See [Boot Stages](#) for more info.

2.4.8 query

Query standardized cloud instance metadata crawled by cloud-init and stored in `/run/cloud-init/instance-data.json`. This is a convenience command-line interface to reference any cached configuration metadata that cloud-init crawls when booting the instance. See [Instance Metadata](#) for more info.

- `--all`: dump all available instance data as json which can be queried
- `--instance-data`: optional path to a different instance-data.json file to source for queries
- `--list-keys`: list available query keys from cached instance data
- `--format`: a string that will use jinja-template syntax to render a string replacing
- `<varname>`: a dot-delimited variable path into the instance-data.json object

Below demonstrates how to list all top-level query keys that are standardized aliases:

```
$ cloud-init query --list-keys
_beta_keys
availability_zone
base64_encoded_keys
cloud_name
ds
instance_id
local_hostname
platform
public_ssh_keys
region
sensitive_keys
subplatform
userdata
v1
vendordata
```

Below demonstrates how to query standardized metadata from clouds:

```
% cloud-init query v1.cloud_name
aws # or openstack, azure, gce etc.

# Any standardized instance-data under a <v#> key is aliased as a top-level key for
↳ convenience.
% cloud-init query cloud_name
aws # or openstack, azure, gce etc.

# Query datasource-specific metadata on EC2
% cloud-init query ds.meta_data.public_ipv4
```

Note: The standardized instance data keys under `v#` are guaranteed not to change behavior or format. If using top-level convenience aliases for any standardized instance data keys, the most value (highest `v#`) of that key name is what is reported as the top-level value. So these aliases act as a ‘latest’.

This data can then be formatted to generate custom strings or data:

```
# Generate a custom hostname fqdn based on instance-id, cloud and region
% cloud-init query --format 'custom-{{instance_id}}.{{region}}.{{v1.cloud_name}}.com'
custom-i-0e91f69987f37ec74.us-east-2.aws.com
```

2.4.9 schema

Validate cloud-config files using jsonschema.

- **-h, --help:** show this help message and exit
- **-c CONFIG_FILE, --config-file CONFIG_FILE:** Path of the cloud-config yaml file to validate
- **--system:** Validate the system cloud-config userdata
- **-d DOCS [DOCS ...], --docs DOCS [DOCS ...]:** Print schema module docs. Choices: all or space-delimited cc_names.
- **--annotate:** Annotate existing cloud-config file with errors

The following example checks a config file and annotates the config file with errors on stdout.

```
$ cloud-init schema -c ./config.yml --annotate
```

2.4.10 single

Attempt to run a single named cloud config module.

- **--name:** the cloud-config module name to run
- **--frequency:** module frequency for this run. One of (always|once-per-instance|once)
- **--report:** enable reporting

The following example re-runs the `cc_set_hostname` module ignoring the module default frequency of once-per-instance:

```
$ cloud-init single --name set_hostname --frequency always
```

Note: Mileage may vary trying to re-run each cloud-config module, as some are not idempotent.

2.4.11 status

Report whether cloud-init is running, done, disabled or errored. Exits non-zero if an error is detected in cloud-init.

- **--long:** detailed status information
- **--wait:** block until cloud-init completes
- **--format [yaml|json|tabular]:** machine-readable JSON or YAML detailed output

Below are examples of output when cloud-init is running, showing status and the currently running modules, as well as when it is done.

```
$ cloud-init status
status: running

$ cloud-init status --long
status: running
time: Fri, 26 Jan 2018 21:39:43 +0000
detail:
Running in stage: init-local

$ cloud-init status
status: done

$ cloud-init status --long
status: done
boot_status_code: enabled-by-generator
last_update: Tue, 16 Aug 2022 19:12:58 +0000
detail:
DataSourceNoCloud [seed=/var/lib/cloud/seed/nocloud-net][dsmode=net]

$ cloud-init status --format=json
{
  "boot_status_code": "enabled-by-generator",
  "datasource": "nocloud",
  "detail": "DataSourceNoCloud [seed=/var/lib/cloud/seed/nocloud-net][dsmode=net]",
  "errors": [],
  "last_update": "Tue, 16 Aug 2022 19:12:58 +0000",
  "status": "done"
}
```

2.5 FAQ

2.5.1 How do I get help?

Having trouble? We would like to help!

- First go through this page with answers to common questions
- Use the search bar at the upper left to search these docs
- Ask a question in the [#cloud-init](#) IRC channel on Libera
- Join and ask questions on the [cloud-init mailing list](#)
- Find a bug? Check out the [Reporting Bugs](#) topic for how to report one

2.5.2 Where are the logs?

Cloud-init uses two files to log to:

- */var/log/cloud-init-output.log*: captures the output from each stage of cloud-init when it runs
- */var/log/cloud-init.log*: very detailed log with debugging output, detailing each action taken
- */run/cloud-init*: contains logs about how cloud-init decided to enable or disable itself, as well as what platforms/datasources were detected. These logs are most useful when trying to determine what cloud-init ran or did not run.

Be aware that each time a system boots, new logs are appended to the files in */var/log*. Therefore, the files may have more than one boot worth of information present.

When reviewing these logs look for any errors or Python tracebacks to check for any errors.

2.5.3 Where are the configuration files?

Cloud-init config is provided in two places:

- */etc/cloud/cloud.cfg*
- */etc/cloud/cloud.cfg.d/*.cfg*

These files can define the modules that run during instance initialization, the datasources to evaluate on boot, and other settings.

See the [configuration sources explanation](#) and [configuration reference](#) for more information.

2.5.4 Where are the data files?

Inside the */var/lib/cloud/* directory there are two important subdirectories:

instance

The */var/lib/cloud/instance* directory is a symbolic link that points to the most recently used instance-id directory. This folder contains the information cloud-init received from datasources, including vendor and user data. This can be helpful to review to ensure the correct data was passed.

It also contains the *datasource* file that contains the full information about what datasource was identified and used to setup the system.

Finally, the *boot-finished* file is the last thing that cloud-init does.

data

The */var/lib/cloud/data* directory contain information related to the previous boot:

- *instance-id*: id of the instance as discovered by cloud-init. Changing this file has no effect.
- *result.json*: json file will show both the datasource used to setup the instance, and if any errors occurred
- *status.json*: json file shows the datasource used and a break down of all four modules if any errors occurred and the start and stop times.

2.5.5 What datasource am I using?

To correctly setup an instance, cloud-init must correctly identify the cloud that it is on. Therefore knowing what datasource is used on an instance launch can help aid in debugging.

To find what datasource is getting used run the *cloud-id* command:

```
$ cloud-id
nocloud
```

If the cloud-id is not what is expected, then running the *ds-identify* script in debug mode and providing that in a bug can help aid in resolving any issues:

```
$ sudo DEBUG_LEVEL=2 DI_LOG=stderr /usr/lib/cloud-init/ds-identify --force
```

The force parameter allows the command to be run again since the instance has already launched. The other options increase the verbosity of logging and put the logs to STDERR.

2.5.6 How can I re-run datasource detection and cloud-init?

If a user is developing a new datasource or working on debugging an issue it may be useful to re-run datasource detection and the initial setup of cloud-init.

To do this, force ds-identify to re-run, clean up any logs, and re-run cloud-init:

```
$ sudo DI_LOG=stderr /usr/lib/cloud-init/ds-identify --force
$ sudo cloud-init clean --logs
$ sudo cloud-init init --local
$ sudo cloud-init init
```

Warning: These commands will re-run cloud-init as if this were first boot of a system: this will, at the very least, cycle SSH host keys and may do substantially more. Do not run these commands on production systems.

2.5.7 How can I debug my user data?

Two of the most common issues with user data, that also happens to be cloud-config is:

1. Incorrectly formatted YAML
2. First line does not contain *#cloud-config*

To verify your YAML, we do have a short script called [validate-yaml.py](#) that can validate your user data offline.

Another option is to run the following on an instance to debug userdata provided to the system:

```
$ cloud-init schema --system --annotate
```

As launching instances in the cloud can cost money and take a bit longer, sometimes it is easier to launch instances locally using Multipass or LXD:

2.5.8 Why did cloud-init never complete?

To check if cloud-init is running still, run:

```
$ cloud-init status
```

To wait for cloud-init to complete, run:

```
$ cloud-init status --wait
```

There are a number of reasons that cloud-init might never complete. This list is not exhaustive, but attempts to enumerate potential causes:

External reasons:

- failed dependent services in the boot
- bugs in the kernel or drivers
- bugs in external userspace tools that are called by cloud-init

Internal reasons:

- a command in `bootcmd` or `runcmd` that never completes (ex: running *cloud-init status --wait* will wait forever on itself and never complete)
- nonstandard configurations that disable timeouts or set extremely high values (“never” is used in a loose sense here)

Failing to Complete on Systemd:

Cloud-init consists of multiple services on systemd. If a service that cloud-init depends on stalls, cloud-init will not continue. If reporting a bug related to cloud-init failing to complete on systemd, please make sure to include the following logs.

```
$ systemd-analyze critical-chain cloud-init.target
$ journalctl --boot=-1
$ systemctl --failed
```

2.5.9 How can I make a module run on every boot?

Modules have a default frequency that can be overridden. This is done by modifying the module list in `/etc/cloud/cloud.cfg`.

1. Change the module from a string (default) to a list.
2. Set the first list item to the module name and the second item to the frequency.

Example

The following example demonstrates how to log boot times to a file every boot.

Update `/etc/cloud/cloud.cfg`:

```
cloud_final_modules:
  # list shortened for brevity
  - [phone-home, always]
  - final-message
  - power-state-change
```

Then your userdata could then be:

```
#cloud-config
phone_home:
  url: http://example.com/$INSTANCE_ID/
  post: all
```

2.5.10 How can I test cloud-init locally before deploying to the cloud?

Several different virtual machine and containerization tools can be used for testing locally. Multipass, LXD, and qemu are described in this section.

Multipass

Multipass is a cross-platform tool to launch Ubuntu VMs across Linux, Windows, and macOS.

When a user launches a Multipass VM, user data can be passed by adding the `-cloud-init` flag and the appropriate YAML file containing user data:

```
$ multipass launch bionic --name test-vm --cloud-init userdata.yaml
```

Multipass will validate the YAML syntax of the cloud-config file before attempting to start the VM! A nice addition to help save time when experimenting with launching instances with various cloud-configs.

Multipass only supports passing user-data and only as YAML cloud-config files. Passing a script, a MIME archive, or any of the other user-data formats cloud-init supports will result in an error from the YAML syntax validator.

LXD

LXD offers a streamlined user experience for using linux system containers. With LXD, a user can pass:

- user data
- vendor data
- metadata
- network configuration

The following initializes a container with user data:

```
$ lxc init ubuntu-daily:bionic test-container
$ lxc config set test-container user.user-data - < userdata.yaml
$ lxc start test-container
```

To avoid the extra commands this can also be done at launch:

```
$ lxc launch ubuntu-daily:bionic test-container --config=user.user-data="$(cat userdata.
↪yaml)"
```

Finally, a profile can be setup with the specific data if a user needs to launch this multiple times:

```
$ lxc profile create dev-user-data
$ lxc profile set dev-user-data user.user-data - < cloud-init-config.yaml
$ lxc launch ubuntu-daily:bionic test-container -p default -p dev-user-data
```

The above examples all show how to pass user data. To pass other types of configuration data use the config option specified below:

Data	Config Option
user data	cloud-init.user-data
vendor data	cloud-init.vendor-data
network config	cloud-init.network-config

See the [LXD Instance Configuration](#) docs for more info about configuration values or the [LXD Custom Network Configuration](#) document for more about custom network config.

QEMU

The *cloud-localds* command from the [cloud-utils](#) package generates a disk with user supplied data. The NoCloud datasouce allows users to provide their own user data, metadata, or network configuration directly to an instance without running a network service. This is helpful for launching local cloud images with QEMU for example.

The following is an example of creating the local disk using the *cloud-localds* command:

```
$ cat >user-data <<EOF
#cloud-config
password: password
chpasswd:
  expire: False
ssh_pwauth: True
ssh_authorized_keys:
  - ssh-rsa AAAA...U1Isqda0+w==
EOF
$ cloud-localds seed.img user-data
```

The resulting *seed.img* can then get passed along to a cloud image containing *cloud-init*. Below is an example of passing the *seed.img* with QEMU:

```
$ qemu-system-x86_64 -m 1024 -net nic -net user \
  -hda ubuntu-20.04-server-cloudimg-amd64.img \
  -hdb seed.img
```

The now booted image will allow for login using the password provided above.

For additional configuration, users can provide much more detailed configuration, including network configuration and metadata:

```
$ cloud-localds --network-config=network-config-v2.yaml \
seed.img userdata.yaml metadata.yaml
```

See the [Networking Config Version 2](#) page for details on the format and config of network configuration. To learn more about the possible values for metadata, check out the [NoCloud](#) page.

2.5.11 Where can I learn more?

Below are some videos, blog posts, and white papers about cloud-init from a variety of sources.

Videos:

- [cloud-init - The Good Parts](#)
- [Perfect Proxmox Template with Cloud Image and Cloud Init \[proxmox, cloud-init, template\]](#)
- [cloud-init - Building clouds one Linux box at a time \(Video\)](#)
- [Metadata and cloud-init](#)
- [Introduction to cloud-init](#)

Blog Posts:

- [cloud-init - The cross-cloud Magic Sauce \(PDF\)](#)
- [cloud-init - Building clouds one Linux box at a time \(PDF\)](#)
- [The beauty of cloud-init](#)
- [Cloud-init Getting Started \[fedora, libvirt, cloud-init\]](#)
- [Build Azure Devops Agents With Linux cloud-init for Dotnet Development \[terraform, azure, devops, docker, dotnet, cloud-init\]](#)
- [Cloud-init Getting Started \[fedora, libvirt, cloud-init\]](#)
- [Setup Neovim cloud-init Completion \[neovim, yaml, Language Server Protocol, jsonschema, cloud-init\]](#)

Events:

- [cloud-init Summit 2019](#)
- [cloud-init Summit 2018](#)
- [cloud-init Summit 2017](#)

Whitepapers:

- [Utilising cloud-init on Microsoft Azure \(Whitepaper\)](#)
- [Cloud Instance Initialization with cloud-init \(Whitepaper\)](#)

2.6 Reporting Bugs

The following documents:

- 1) How to collect information for reporting bugs
- 2) How to file bugs to the upstream cloud-init project or for distro specific packages

2.6.1 Collect Logs

To aid in debugging, please collect the necessary logs. To do so, run the *collect-logs* subcommand to produce a tarfile that you can easily upload:

```
$ sudo cloud-init collect-logs
Wrote /home/ubuntu/cloud-init.tar.gz
```

If your version of cloud-init does not have the *collect-logs* subcommand, then please manually collect the base log files by doing the following:

```
$ sudo dmesg > dmesg.txt
$ sudo journalctl -o short-precise > journal.txt
$ sudo tar -cvf cloud-init.tar dmesg.txt journal.txt /run/cloud-init \
  /var/log/cloud-init.log /var/log/cloud-init-output.log
```

2.6.2 Report Upstream Bug

Bugs for upstream cloud-init are tracked using Launchpad. To file a bug:

1. Collect the necessary debug logs as described above
2. [Create a Launchpad account](#) or login to your existing account
3. [Report an upstream cloud-init bug](#)

If debug logs are not provided, you will be asked for them before any further time is spent debugging. If you are unable to obtain the required logs please explain why in the bug.

If your bug is for a specific distro using cloud-init, please first consider reporting it with the upstream distro or confirm that it still occurs with the latest upstream cloud-init code. See below for details on specific distro reporting.

2.6.3 Distro Specific Issues

For issues specific to your distro please use one of the following distro specific reporting mechanisms:

Ubuntu

To report a bug on Ubuntu use the *ubuntu-bug* command on the affected system to automatically collect the necessary logs and file a bug on Launchpad:

```
$ ubuntu-bug cloud-init
```

If that does not work or is not an option, please collect the logs using the commands in the above Collect Logs section and then report the bug on the [Ubuntu bug tracker](#). Make sure to attach your collected logs!

Debian

To file a bug against the Debian package for cloud-init please use the [Debian bug tracker](#) to file against 'Package: cloud-init'. See the [Debian bug reporting wiki](#) page for more details.

Red Hat, CentOS, & Fedora

To file a bug against the Red Hat or Fedora packages of cloud-init please use the [Red Hat bugzilla](#).

SUSE & openSUSE

To file a bug against the SuSE packages of cloud-init please use the [SUSE bugzilla](#).

Arch Linux

To file a bug against the Arch package of cloud-init please use the [Arch Linux Bugtracker](#). See the [Arch Linux bug reporting wiki](#) for more details.

2.7 Configuration Sources

Internally, cloud-init builds a single configuration that is then referenced throughout the life of cloud-init. The configuration is built from multiple sources such that if a key is defined in multiple sources, the higher priority source overwrites the lower priority source.

2.7.1 Base Configuration

From lowest priority to highest, configuration sources are:

- **Hardcoded config:** [Config](#) that lives within the source of cloud-init and cannot be changed.
- **Configuration directory:** Anything defined in `/etc/cloud/cloud.cfg` and `/etc/cloud/cloud.cfg.d`.
- **Runtime config:** Anything defined in `/run/cloud-init/cloud.cfg`.
- **Kernel command line:** On the kernel command line, anything found between `cc:` and `end_cc` will be interpreted as cloud-config user data.

These four sources make up the base configuration.

2.7.2 Vendor and User Data

Added to the base configuration are:

- **Vendor data:** *Data* provided by the datasource
- **User data:** *Data* also provided by the datasource

These get fetched from the datasource and are defined at instance launch.

Note: While much of what is defined in the base configuration can be overridden by vendor data and user data, base configuration sources do not conform to *#cloud-config*

2.7.3 Network Configuration

Network configuration happens independently from other cloud-init configuration. See *network configuration documentation* for more information.

2.7.4 Specifying Configuration

End users

Pass *user data* to the cloud provider. Every platform supporting cloud-init will provide a method of supplying user data. If you're unsure how to do this, reference the documentation provided by the cloud platform you're on. Additionally, there may be related cloud-init documentation in the *datasource* section.

Once an instance has been initialized, the user data may not be edited. It is sourced directly from the cloud, so even if you find a local file that contains user data, it will likely be overwritten next boot.

Distro Providers

Modify the base config. This often involves submitting a PR to modify the base *cloud.cfg* template, which is used to customize */etc/cloud/cloud.cfg* per distro. Additionally, a file can be added to */etc/cloud/cloud.cfg.d* to override a piece of the base configuration.

Cloud Providers

Pass vendor data. This is the preferred method for clouds to provide their own customization. In some cases, it may make sense to modify the base config in the same manner as distro providers on cloud-supported images.

2.8 User-Data Formats

User data that will be acted upon by cloud-init must be in one of the following types.

2.8.1 Cloud Config Data

Cloud-config is the simplest way to accomplish some things via user-data. Using cloud-config syntax, the user can specify certain things in a human friendly format.

These things include:

- apt upgrade should be run on first boot
- a different apt mirror should be used
- additional apt sources should be added
- certain SSH keys should be imported
- *and many more...*

Note: This file must be valid YAML syntax.

See the [Cloud config examples](#) section for a commented set of examples of supported cloud config formats.

Begins with: `#cloud-config` or `Content-Type: text/cloud-config` when using a MIME archive.

Note: New in cloud-init v. 18.4: Cloud config data can also render cloud instance metadata variables using jinja templating. See [Instance Metadata](#) for more information.

2.8.2 User-Data Script

Typically used by those who just want to execute a shell script.

Begins with: `#!/` or `Content-Type: text/x-shellscript` when using a MIME archive.

Note: New in cloud-init v. 18.4: User-data scripts can also render cloud instance metadata variables using jinja templating. See [Instance Metadata](#) for more information.

Example

```
$ cat myscript.sh

#!/bin/sh
echo "Hello World. The time is now $(date -R)!" | tee /root/output.txt

$ euca-run-instances --key mykey --user-data-file myscript.sh ami-a07d95c9
```

2.8.3 Kernel Command Line

When using the *NoCloud* datasource, users can pass user data via the kernel command line parameters. See the *NoCloud* datasource and *Kernel Command Line* documentations for more details.

2.8.4 Gzip Compressed Content

Content found to be gzip compressed will be uncompressed. The uncompressed data will then be used as if it were not compressed. This is typically useful because user-data is limited to ~16384¹ bytes.

2.8.5 Mime Multi Part Archive

This list of rules is applied to each part of this multi-part file. Using a mime-multi part file, the user can specify more than one type of data.

For example, both a user data script and a cloud-config type could be specified.

Supported content-types are listed from the cloud-init subcommand make-mime:

```
$ cloud-init devel make-mime --list-types
cloud-boothook
cloud-config
cloud-config-archive
cloud-config-jsonp
jinja2
part-handler
x-include-once-url
x-include-url
x-shellscript
x-shellscript-per-boot
x-shellscript-per-instance
x-shellscript-per-once
```

Helper subcommand to generate mime messages

The cloud-init subcommand can generate MIME multi-part files: `make-mime`.

`make-mime` subcommand takes pairs of (filename, “text/” mime subtype) separated by a colon (e.g. `config.yaml:cloud-config`) and emits a MIME multipart message to stdout.

Examples

Create userdata containing both a cloud-config (`config.yaml`) and a shell script (`script.sh`)

```
$ cloud-init devel make-mime -a config.yaml:cloud-config -a script.sh:x-shellscript >┐
↪userdata
```

Create userdata containing 3 shell scripts:

- `always.sh` - Run every boot
- `instance.sh` - Run once per instance

¹ See your cloud provider for applicable user-data size limitations...

- `once.sh` - Run once

```
$ cloud-init devel make-mime -a always.sh:x-shellscript-per-boot -a instance.sh:x-shellscript-per-instance -a once.sh:x-shellscript-per-once
```

2.8.6 Include File

This content is a `include` file.

The file contains a list of urls, one per line. Each of the URLs will be read, and their content will be passed through this same set of rules. I.e., the content read from the URL can be gzipped, mime-multi-part, or plain text. If an error occurs reading a file the remaining files will not be read.

Begins with: `#include` or `Content-Type: text/x-include-url` when using a MIME archive.

2.8.7 Cloud Boothook

This content is `boothook` data. It is stored in a file under `/var/lib/cloud` and then executed immediately. This is the earliest hook available. Note, that there is no mechanism provided for running only once. The boothook must take care of this itself.

It is provided with the instance id in the environment variable `INSTANCE_ID`. This could be made use of to provide a 'once-per-instance' type of functionality.

Begins with: `#cloud-boothook` or `Content-Type: text/cloud-boothook` when using a MIME archive.

2.8.8 Part Handler

This is a `part-handler`: It contains custom code for either supporting new mime-types in multi-part user data, or overriding the existing handlers for supported mime-types. It will be written to a file in `/var/lib/cloud/data` based on its filename (which is generated).

This must be python code that contains a `list_types` function and a `handle_part` function. Once the section is read the `list_types` method will be called. It must return a list of mime-types that this part-handler handles. Because mime parts are processed in order, a `part-handler` part must precede any parts with mime-types it is expected to handle in the same user data.

The `handle_part` function must be defined like:

```
def handle_part(data, ctype, filename, payload):
    # data = the cloudinit object
    # ctype = "__begin__", "__end__", or the mime-type of the part that is being handled.
    # filename = the filename of the part (or a generated filename if none is present in
    # mime data)
    # payload = the parts' content
```

Cloud-init will then call the `handle_part` function once before it handles any parts, once per part received, and once after all parts have been handled. The `'__begin__'` and `'__end__'` sentinels allow the part handler to do initialization or teardown before or after receiving any parts.

Begins with: `#part-handler` or `Content-Type: text/part-handler` when using a MIME archive.

Example

```
1 #part-handler
2
3 def list_types():
4     # return a list of mime-types that are handled by this module
5     return(["text/plain", "text/go-cubs-go"])
6
7 def handle_part(data, ctype, filename, payload):
8     # data: the cloudinit object
9     # ctype: '__begin__', '__end__', or the specific mime-type of the part
10    # filename: the filename for the part, or dynamically generated part if
11    #           no filename is given attribute is present
12    # payload: the content of the part (empty for begin or end)
13    if ctype == "__begin__":
14        print("my handler is beginning")
15        return
16    if ctype == "__end__":
17        print("my handler is ending")
18        return
19
20    print(f"==== received ctype={ctype} filename={filename} ====")
21    print(payload)
22    print(f"==== end ctype={ctype} filename={filename}")
```

Also this [blog](#) post offers another example for more advanced usage.

2.8.9 Disabling User-Data

Cloud-init can be configured to ignore any user-data provided to instance. This allows custom images to prevent users from accidentally breaking closed appliances. Setting `allow_userdata: false` in the configuration will disable cloud-init from processing user-data.

2.9 Cloud config examples

2.9.1 Including users and groups

```
1 #cloud-config
2 # Add groups to the system
3 # The following example adds the 'admingroup' group with members 'root' and 'sys'
4 # and the empty group cloud-users.
5 groups:
6     - admingroup: [root,sys]
7     - cloud-users
8
9 # Add users to the system. Users are added after groups are added.
10 # Note: Most of these configuration options will not be honored if the user
11 #       already exists. Following options are the exceptions and they are
12 #       applicable on already-existing users:
13 #       - 'plain_text_passwd', 'hashed_passwd', 'lock_passwd', 'sudo',
```

(continues on next page)

(continued from previous page)

```

14 # 'ssh_authorized_keys', 'ssh_redirect_user'.
15 users:
16 - default
17 - name: foobar
18   gecos: Foo B. Bar
19   primary_group: foobar
20   groups: users
21   selinux_user: staff_u
22   expiredate: '2032-09-01'
23   ssh_import_id:
24     - lp:falcojr
25     - gh:TheRealFalcon
26   lock_passwd: false
27   passwd: $6$j212wezy$7H/1LT4f9/N3wpgNunhsIqtMj620KiS3nyNwui zouQc3u7MbYCarYeAHWYPYb2FT.
    ↳lbioDm2RrkJPb9BZMN10/
28 - name: barfoo
29   gecos: Bar B. Foo
30   sudo: ALL=(ALL) NOPASSWD:ALL
31   groups: users, admin
32   ssh_import_id:
33     - lp:falcojr
34     - gh:TheRealFalcon
35   lock_passwd: true
36   ssh_authorized_keys:
37     - ssh-rsa AAAAB3NzaC1yc2EAAAADAQABAAQDSL7uWGj8cgWyIOaspgKdVy0cKJ+UTjfv7jB0jG2H/
    ↳GN8bJVXy72XAvnhM0dUM+CCs8F0f0YlPX+FrVz2hKInrmRhZVwRSL129PasD12MlI3l44u6IwS1o/
    ↳W86Q+tkQYEljtd0o0a+c0saZkvUNzUyEXUwz/
    ↳lmYa6G4hMKZH4NBj7nbAAF96wsMCoyNwbWryBnDYUr6wMbjRR1J9Pw7Xh7WRC73wy4Va2YuOgbD3V/
    ↳5ZrFPLbWZW/7TFXVrql04QVbyei4aiFR5n//GvoqwQDN58LmbzX/xvxyKJYdny2zXmdAhMxbrpFQsfpkJ9E/
    ↳H5w0yOdSvnWbUoG5xNGoOB csmith@fringe
38 - name: cloudy
39   gecos: Magic Cloud App Daemon User
40   inactive: '5'
41   system: true
42 - name: fizzbuzz
43   sudo: false
44   shell: /bin/bash
45   ssh_authorized_keys:
46     - ssh-rsa AAAAB3NzaC1yc2EAAAADAQABAAQDSL7uWGj8cgWyIOaspgKdVy0cKJ+UTjfv7jB0jG2H/
    ↳GN8bJVXy72XAvnhM0dUM+CCs8F0f0YlPX+FrVz2hKInrmRhZVwRSL129PasD12MlI3l44u6IwS1o/
    ↳W86Q+tkQYEljtd0o0a+c0saZkvUNzUyEXUwz/
    ↳lmYa6G4hMKZH4NBj7nbAAF96wsMCoyNwbWryBnDYUr6wMbjRR1J9Pw7Xh7WRC73wy4Va2YuOgbD3V/
    ↳5ZrFPLbWZW/7TFXVrql04QVbyei4aiFR5n//GvoqwQDN58LmbzX/xvxyKJYdny2zXmdAhMxbrpFQsfpkJ9E/
    ↳H5w0yOdSvnWbUoG5xNGoOB csmith@fringe
47 - snapuser: joe@joeuser.io
48 - name: nosshlogins
49   ssh_redirect_user: true
50
51 # Valid Values:
52 #   name: The user's login name
53 #   expiredate: Date on which the user's account will be disabled.
54 #   gecos: The user name's real name, i.e. "Bob B. Smith"

```

(continues on next page)

(continued from previous page)

```

55 # homedir: Optional. Set to the local path you want to use. Defaults to
56 #     /home/<username>
57 # primary_group: define the primary group. Defaults to a new group created
58 #     named after the user.
59 # groups: Optional. Additional groups to add the user to. Defaults to none
60 # selinux_user: Optional. The SELinux user for the user's login, such as
61 #     "staff_u". When this is omitted the system will select the default
62 #     SELinux user.
63 # lock_passwd: Defaults to true. Lock the password to disable password login
64 # inactive: Number of days after password expires until account is disabled
65 # passwd: The hash -- not the password itself -- of the password you want
66 #     to use for this user. You can generate a hash via:
67 #         mkpasswd --method=SHA-512 --rounds=4096
68 #     (the above command would create from stdin an SHA-512 password hash
69 #     with 4096 salt rounds)
70 #
71 #     Please note: while the use of a hashed password is better than
72 #     plain text, the use of this feature is not ideal. Also,
73 #     using a high number of salting rounds will help, but it should
74 #     not be relied upon.
75 #
76 #     To highlight this risk, running John the Ripper against the
77 #     example hash above, with a readily available wordlist, revealed
78 #     the true password in 12 seconds on a i7-2620QM.
79 #
80 #     In other words, this feature is a potential security risk and is
81 #     provided for your convenience only. If you do not fully trust the
82 #     medium over which your cloud-config will be transmitted, then you
83 #     should not use this feature.
84 #
85 # no_create_home: When set to true, do not create home directory.
86 # no_user_group: When set to true, do not create a group named after the user.
87 # no_log_init: When set to true, do not initialize lastlog and faillog database.
88 # ssh_import_id: Optional. Import SSH ids
89 # ssh_authorized_keys: Optional. [list] Add keys to user's authorized keys file
90 #     An error will be raised if no_create_home or system is
91 #     also set.
92 # ssh_redirect_user: Optional. [bool] Set true to block ssh logins for cloud
93 #     ssh public keys and emit a message redirecting logins to
94 #     use <default_username> instead. This option only disables cloud
95 #     provided public-keys. An error will be raised if ssh_authorized_keys
96 #     or ssh_import_id is provided for the same user.
97 #
98 # sudo: Defaults to none. Accepts a sudo rule string, a list of sudo rule
99 #     strings or False to explicitly deny sudo usage. Examples:
100 #
101 #     Allow a user unrestricted sudo access.
102 #     sudo: ALL=(ALL) NOPASSWD:ALL
103 #
104 #     Adding multiple sudo rule strings.
105 #     sudo:
106 #         - ALL=(ALL) NOPASSWD:/bin/mysql

```

(continues on next page)

(continued from previous page)

```

107 #           - ALL=(ALL) ALL
108 #
109 #       Prevent sudo access for a user.
110 #       sudo: False
111 #
112 #       Note: Please double check your syntax and make sure it is valid.
113 #             cloud-init does not parse/check the syntax of the sudo
114 #             directive.
115 #       system: Create the user as a system user. This means no home directory.
116 #       snapuser: Create a Snappy (Ubuntu-Core) user via the snap create-user
117 #                 command available on Ubuntu systems. If the user has an account
118 #                 on the Ubuntu SSO, specifying the email will allow snap to
119 #                 request a username and any public ssh keys and will import
120 #                 these into the system with username specified by SSO account.
121 #                 If 'username' is not set in SSO, then username will be the
122 #                 shortname before the email domain.
123 #
124
125 # Default user creation:
126 #
127 # Unless you define users, you will get a 'ubuntu' user on Ubuntu systems with the
128 # legacy permission (no password sudo, locked user, etc). If however, you want
129 # to have the 'ubuntu' user in addition to other users, you need to instruct
130 # cloud-init that you also want the default user. To do this use the following
131 # syntax:
132 #   users:
133 #       - default
134 #       - bob
135 #       - ....
136 #   foobar: ...
137 #
138 # users[0] (the first user in users) overrides the user directive.
139 #
140 # The 'default' user above references the distro's config:
141 # system_info:
142 #   default_user:
143 #       name: Ubuntu
144 #       plain_text_passwd: 'ubuntu'
145 #       home: /home/ubuntu
146 #       shell: /bin/bash
147 #       lock_passwd: True
148 #       gecos: Ubuntu
149 #       groups: [adm, audio, cdrom, dialout, floppy, video, plugdev, dip, netdev]

```

2.9.2 Writing out arbitrary files

```

1 #cloud-config
2 # vim: syntax=yaml
3 #
4 # This is the configuration syntax that the write_files module
5 # will know how to understand. Encoding can be given b64 or gzip or (gz+b64).
6 # The content will be decoded accordingly and then written to the path that is
7 # provided.
8 #
9 # Note: Content strings here are truncated for example purposes.
10 write_files:
11 - encoding: b64
12   content: CiMgVGhpcyBmaWxlIGNvbnRyb2xzIHRoZSBzdGF0ZSBvZiBTRUxpbnV4...
13   owner: root:root
14   path: /etc/sysconfig/selinux
15   permissions: '0644'
16 - content: |
17     # My new /etc/sysconfig/samba file
18
19     SMBDOPTIONS="-D"
20   path: /etc/sysconfig/samba
21 - content: !!binary |
22     f0VMRgIBAQAAAAAAAAAAAAIAPgABAAAAwAAAAAAAAABAAAAAAAAAAJAVAAAAAAAAAAAAEAAOAAI
23     AEAHGAAdAAAYAAAAFAAAAAQAAAAAAAAABAAEAAAAAAAAEAAQAAAAAAAAAwEAAAAAAAAADAAQAAAAAAAAAgA
24     AAAAAAAAAAwAAAAQAAAAAAAgAAAAAAAAAACQAAAAAAAAAAJAAAAAAAAAcAAAAAAAAABwAAAAAAAAAQAA
25     ....
26   path: /bin/arch
27   permissions: '0555'
28 - encoding: gzip
29   content: !!binary |
30     H4sIAIDb/U8C/1NW1E/KzNMvzuBKTc7IV8hIzcnJVyJPL8pJ4QIA6N+MVxsAAAA=
31   path: /usr/bin/hello
32   permissions: '0755'

```

2.9.3 Adding a yum repository

```

1 #cloud-config
2 # vim: syntax=yaml
3 #
4 # Add yum repository configuration to the system
5 #
6 # The following example adds the file /etc/yum.repos.d/epel_testing.repo
7 # which can then subsequently be used by yum for later operations.
8 yum_repos:
9   # The name of the repository
10   epel-testing:
11     # Any repository configuration options
12     # See: man yum.conf
13     #
14     # This one is required!

```

(continues on next page)

(continued from previous page)

```

15  baseurl: http://download.fedoraproject.org/pub/epel/testing/5/$basearch
16  enabled: false
17  failovermethod: priority
18  gpgcheck: true
19  gpgkey: file:///etc/pki/rpm-gpg/RPM-GPG-KEY-EPEL
20  name: Extra Packages for Enterprise Linux 5 - Testing

```

2.9.4 Configure an instances trusted CA certificates

```

1  #cloud-config
2  #
3  # This is an example file to configure an instance's trusted CA certificates
4  # system-wide for SSL/TLS trust establishment when the instance boots for the
5  # first time.
6  #
7  # Make sure that this file is valid yaml before starting instances.
8  # It should be passed as user-data when starting the instance.
9
10 ca_certs:
11   # If present and set to True, the 'remove_defaults' parameter will remove
12   # all the default trusted CA certificates that are normally shipped with
13   # Ubuntu.
14   # This is mainly for paranoid admins - most users will not need this
15   # functionality.
16   remove_defaults: true
17
18   # If present, the 'trusted' parameter should contain a certificate (or list
19   # of certificates) to add to the system as trusted CA certificates.
20   # Pay close attention to the YAML multiline list syntax. The example shown
21   # here is for a list of multiline certificates.
22   trusted:
23   - |
24     -----BEGIN CERTIFICATE-----
25     YOUR-ORGS-TRUSTED-CA-CERT-HERE
26     -----END CERTIFICATE-----
27   - |
28     -----BEGIN CERTIFICATE-----
29     YOUR-ORGS-TRUSTED-CA-CERT-HERE
30     -----END CERTIFICATE-----

```

2.9.5 Install and run chef recipes

```

1  #cloud-config
2  #
3  # This is an example file to automatically install chef-client and run a
4  # list of recipes when the instance boots for the first time.
5  # Make sure that this file is valid yaml before starting instances.
6  # It should be passed as user-data when starting the instance.
7

```

(continues on next page)

(continued from previous page)

```

8  # The default is to install from packages.
9
10 # Key from https://packages.chef.io/chef.asc
11 apt:
12   sources:
13     source1:
14       source: "deb http://packages.chef.io/repos/apt/stable $RELEASE main"
15       key: |
16         -----BEGIN PGP PUBLIC KEY BLOCK-----
17         Version: GnuPG v1.4.12 (Darwin)
18         Comment: GPGTools - http://gpgtools.org
19
20         mQGiBEppC7QRBADfsOkZU6KZK+YmKw4wev5mjKJEkVGlus+NxW8wItX5sGa6kdUu
21         twAyj7Yr92rF+ICFEP3gGU6+lGo0Nve7KxkN/1W7/m3G4zuk+ccIKmjp8KS3qn99
22         dxy64vcji9jI1lVa+XXOGIp0G8GEaj7mbkixL/bMeGfdMlv8Gf2XPPp9vwCgn/GC
23         JKacfnw7MplKUHOYS1b//JsEAJqao3ViNfav83jJKEkD8cf59Y8xKia5OpZqTK5W
24         ShVnNWS3U5IVQk10ZDH97Qn/YrK387H4CyhLE9mxPXs/ul18ioiaars/q2MEKU2I
25         XKfv21eMLO9LYd6Ny/Kqj8o5WQK2J6+NAhSwvthZcIEphcFignIuobP+B5wNFQpe
26         DbKfA/0WvN2OwFeWRcmmd3Hz7nHTpcnSF+4QX6yHRF/5BgxkG6IqBIACQbzPn6Hm
27         sMtm/SVf11izmDqSsQptCrOZILfLX/mE+YOl+CwWSHh1+YsFts1W0uh1EhQD26aO
28         Z84HuHV5HFRWjDLw9LriltBVQcXbpfSrRP5bdr7Wh8vhqJTPjrQnT3BzY29kZSBQ
29         YWNRyWdlcyA8cGFja2FnZXNAb3BzY29kZS5jb20+iGAEExECACAFakppC7QCGwMG
30         CwkIBwMCBBUCCAMEFgIDAQIeAQIXgAAKCRApQKupg++Caj8sAKCOXmdG36gWji/K
31         +o+XtBfvdMnFYQCfTCEWxRy2BnzLoBBFCjDSK6sJqCu0IENIRUYgUGFja2FnZXMG
32         PHBhY2thZ2VzQGNoZWYuaW8+iGIEExECACIFAlQwYFECGwMGCwkIBwMCBhUIAgkK
33         CwQWAgMBAh4BAheAAAJECIAq6mD74JqX94An26z99XOHwPLN8ahzm7cp13t4Xid
34         AJ9wVcgoUBzvgg911Kfv/34cmemZn7kCDQRKaQu0EAgAg7ZLCVGVtMlQBM6njZEd
35         Zbv+mZbvWLBsOmddE6u3eH0X3GuwaQfQWHUVG2yedyDMiG+EMtCdEeeRebTCz
36         SNXQ8Xvi22hRPoEsBSwWLZI8/XNg0n0f1+GER+mOKO0BxDB2DG7DA0nnEISxwFkK
37         OFJFebR3fRsrWjj0KjDxkhse2ddU/jVz1BY7Nf8toZmwpBmdozETMOTx3LJy1HZ/
38         Te9FJXJMUaB2lRyluv15MVWCKQJro4MQG/7QGcIfrIZNfAGJ32DDsjV7/YO+IpRY
39         IL4CUBQ65suY4gYUG4jhRH6u7H1p99sdwsg50IpBe/v2Vbc/tbwAB+eJJAp89Zeu
40         twADBQf/ZcGoPhTGFuzbkcnRSIz+boaewPoSxK2DyfScyCAuG41CY9+g0HIw9Sq8
41         DuxQvJ+vrEJjNvNE3EAEdKl/zkXmZdb1EXjGwDi845TxEMhhd1dDw2qpHqnJ2mtE
42         WpZ7juGwA3sGhi6Fap004tIGacCfNNHmlRGipyq5ZiKIRq9mLEndIECr8cwaKgkS
43         0wWu+xmMZe7N5/t/TK19HXNh4tVacv0F3fYK54GUjt2FjCQV75USnmNY4KPTYLXA
44         dzC364hEMlXpN21siIFgB04w+TXn5UF3B4FfAy5hevvr4DtV4MvMiGLu0oWjpaLC
45         MpmrR3Ny2wkm00h+vgri9uIP06ODWIhJBBgRagAJBQJKAQu0AhsMAAoJECIAq6mD
46         74Jq4hIAoJ5KrYS8kCwj26SAGzg1wggpvvt3CAJ0bekyky56vNqoegB+y4PQVDv4K
47         zA==
48         =IxPr
49         -----END PGP PUBLIC KEY BLOCK-----
50
51 chef:
52
53   # Valid values are 'accept' and 'accept-no-persist'
54   chef_license: "accept"
55
56   # Valid values are 'gems' and 'packages' and 'omnibus'
57   install_type: "packages"
58
59   # Boolean: run 'install_type' code even if chef-client

```

(continues on next page)

(continued from previous page)

```

60  #           appears already installed.
61  force_install: false
62
63  # Chef settings
64  server_url: "https://chef.yourorg.com"
65
66  # Node Name
67  # Defaults to the instance-id if not present
68  node_name: "your-node-name"
69
70  # Environment
71  # Defaults to '_default' if not present
72  environment: "production"
73
74  # Default validation name is chef-validator
75  validation_name: "yourorg-validator"
76  # if validation_cert's value is "system" then it is expected
77  # that the file already exists on the system.
78  validation_cert: |
79      -----BEGIN RSA PRIVATE KEY-----
80      YOUR-ORGS-VALIDATION-KEY-HERE
81      -----END RSA PRIVATE KEY-----
82
83  # A run list for a first boot json, an example (not required)
84  run_list:
85      - "recipe[apache2]"
86      - "role[db]"
87
88  # Specify a list of initial attributes used by the cookbooks
89  initial_attributes:
90      apache:
91          prefork:
92              maxclients: 100
93              keepalive: "off"
94
95  # if install_type is 'omnibus', change the url to download
96  omnibus_url: "https://www.chef.io/chef/install.sh"
97
98  # if install_type is 'omnibus', pass pinned version string
99  # to the install script
100  omnibus_version: "12.3.0"
101
102  # If encrypted data bags are used, the client needs to have a secrets file
103  # configured to decrypt them
104  encrypted_data_bag_secret: "/etc/chef/encrypted_data_bag_secret"
105
106  # Capture all subprocess output into a logfile
107  # Useful for troubleshooting cloud-init issues
108  output: {all: '| tee -a /var/log/cloud-init-output.log'}

```

2.9.6 Install and run *ansible-pull*

```

1 #cloud-config
2 packages_update: true
3 packages_upgrade: true
4
5 # if you're already installing other packages, you may
6 # wish to manually install ansible to avoid multiple calls
7 # to your package manager
8 packages:
9   - git
10 ansible:
11   install_method: pip
12   pull:
13     url: "https://github.com/holmanb/vmboot.git"
14     playbook_name: ubuntu.yml

```

2.9.7 Configure Instance to be Managed by Ansible

```

1 #cloud-config
2 #
3 # A common use-case for cloud-init is to bootstrap user and ssh
4 # settings to be managed by a remote configuration management tool,
5 # such as ansible.
6 #
7 # This example assumes a default Ubuntu cloud image, which should contain
8 # the required software to be managed remotely by Ansible.
9 #
10 ssh_pwauth: false
11
12 users:
13 - name: ansible
14   gecol: Ansible User
15   groups: users,admin,wheel
16   sudo: ALL=(ALL) NOPASSWD:ALL
17   shell: /bin/bash
18   lock_passwd: true
19   ssh_authorized_keys:
20     - "ssh-rsa
21     ↪AAAAB3NzaC1yc2EAAAADAQABAAQGDRCJCQ1UD9QslWDSw5Pwsvba0Wsf1p04how5BtNaZn0xLZpTq2nqFEJshUkd/
22     ↪zCWF7DWyhmNphQ8c+U+wcmdNVcg2pI1kPxq0VZzBfZ7cDwhjgeLsIvTXvU+HVRtsXh4c5FlUXpRj f/
23     ↪x+a3vqFRvNsRd1DE+5ZqQHbOVbnsStk3PZppaByMg+AZZMx56OUk2pZCgvpCwj6LIixqwuxNKPxmJf45RyOsPUXwCwkq9UD4me5jk.
24     ↪141moWsGxSnd5NxCbPUWGoRfYcHc865E70nN4WrZkM7RFI/s5mvQtuj8dRL67JUEwvdvED00EBz21FV/
25     ↪iOracXd2omlTUSK+wYrWGtiwQwEgr4r5bimxDKy9L8UlaJZ+ONhLTP8ecTHYkaU1C75sLX9ZYd5YtqjiNgSNF+wdW6WrXrQiWeyrG
26     ↪"
27
28 # use the following passwordless demonstration key for testing or
29 # replace with your own key pair
30 #
31 # -----BEGIN OPENSSH PRIVATE KEY-----

```

(continues on next page)

(continued from previous page)

```

27 # b3BlbnNzaC1rZXktbjEAAAAABG5vbmUAAAAEbm9uZQAAAAAAAAABAAABlwAAAAAdzc2gtcn
28 # NhAAAAAwEAAQAAAYEA0QIQkNVA/ULJVg0sOT8LL22tFrH9aTuIaMOQbTWmZ9MS2aU6tp6h
29 # RChIVJHf8w1hew1soZjaYUPHP1PsHJnTVXINqSNZD8atFWcwX2e3A8IY4Hi7CL0171Ph1U
30 # bbF4eHORZVF6UY3/8fmt76hUbzbEXdQxPuWakB2z1W57ErZNz2aaWgcjIPgGWTMeej1JNq
31 # WQoL6QsI+iyIsasLsTSj8ZiX+OUcjrD1F8AsJKvVA+JnuY5LEzz5Ld6H1FsNWUkhfBf9eN
32 # ZqFrBsUp3eTcQmz1FhqEX2HB3POuR09JzeFq2ZD00RSP70Zr0Lbo/HUS+uyVBML3bxAZtB
33 # Ac9tRVf4j4q2nF3dqJpU1EivsGK1hrYsEMBIK+K+W4psQysvS/FJWiWfjjYS0z/HnEx2JG1
34 # NQu+bC1/WWHeWLao4jRrDRfsHVulq160Ilnsqxiu2cGw05WoEsSGu8nqpyg43ZHCb0FwmB
35 # izPQDASlniWjqcKmfTrpzAy3eVWaww1NpaQkidTAAAFgKGSj8diko/HAAAAAB3NzaC1yc2
36 # EAAAGBANeIkjDVQP1CyVYNLDk/Cy9trRax/Wk7iGjDkG01pmfTEtm10raeoUQmyFSR3/MJ
37 # YXsNbKGY2mFDxz5T7ByZ01VyDakjWQ/GrRVnMF9ntwPCGOB4uwi9Ne9T4dVG2xeHhZkWVR
38 # e1GN//H5re+oVG82xf3UMT7lmpAds5VuexK2Tc9mmloHIyD4BlkzHno5STalkKC+kLCPos
39 # iLGrC7E0o/GY1/jlHI6w9RfALCSr1QPiZ7m0SxM8+S3eh5RbDVLJIXwX/XjWahawbFKd3k
40 # 3EJS9RYahF9hwdzzrkTvSc3hatmQztEUj+zma9C26Px1Evrs1QTC928QM7QQHPbUVX+I6t
41 # pxd3aiaVNRir7BitYa2LBDASCviviluKbEMrL0vxSVoln442EtM/x5xMdiRpTULvmwtf1lh
42 # 3li2qOI0aw0X7B1bpatetCJZ7KsYrtnBsDuVqBLEhrvJ6qcoON2Rwm9BcJgYsz0AwEpZ4l
43 # o6nCPn5066cwMt3lVmsMJTaWkJInUwAAAAABAAEAAAGAEuz77Hu9EEZyujL0dTnAW9afRv
44 # XDOZA6pS7yWEufjw5CS1MLwisR83yww09t1QWYvhRqEyYmv0BecsXgaSUtnYfftWz44apy
45 # /gQYvMVELGKaJAC/q7vjMpGyrxUPkyLMhckALU2KYgV+/rj/j6pBMeVlchmk3pikYrffUX
46 # JDY990WVO194Dm0buLRzJvfMKYF2BcfF4TvarjOXWAXSuR8www050oJ8HdKahW7Cm5S0po
47 # FRnNXFGMnLA62vN00vJW8V7j7vui9ukBbhjRWaJuY5rdG/UYmzAe4wvdIEnpk9xIn6JGCp
48 # FRYTRn7lTh5+/QlQ6FXRP8Ir1vXZFnhKz10K8Vqh2sf4M79MsIUGAQGxg9xdhjIa5dmgp8
49 # N18IEDoNEVKUbKuKe/Z5yf8Z9tmexfH1YttjmXMO0jBvUHIjRS5hdI9NxnPGRLY2kjAzcm
50 # gV9Rv3vtdF/+zalk3fAVLeK8hXK+di/7XTvYpfJ2EZBWiNrTeagfNNGiYydsQy3zjZAAAA
51 # wBNRak7UrqNlHMZn7pkCTgceb1MfByaFtlNzd+Obah54HYIQj5WdZTBAITReMZNt9S5NAR
52 # M8sQB8UoZPaVSC3ppILiOfLhs6KYj6RrGdiYwyIhMPJ5kRWF8xGCLUX5CjwH2EOq7XhIWt
53 # MwEFtd/gF2Du7HUNFPsZGnzJ3e7pDKDnE7w2khZ8CIpTFgD769uBYGAtk45QYTD05JroVM
54 # ZPDq08Gb/RhIgJLmIpMwyreVpLLLe8SwoMJJ+rihmnJZx08gAAAMEA0lhiKezeTshht4xu
55 # rWc0NxxD84a29gSGfTphDP0rlKSEYbkSXhjQCsAZHd8S8kMr3iF6poOk3IWSvFJ6mbd3ie
56 # qdRTgXH9Thwk4KgpjUhnSQuYRHBbI59Mo+BxSI1B1qzmJSGdmCBL54wwzZmFKDQPQKPxIL
57 # n0Mlc7GooiDMjT1tbuW/01EL5EqTRqwgWPTKhBA6r4PnGF150hZRIMooZkD2zX6b1sGojk
58 # QpvKkEyKtwnKczF5TX08+wJ3qbcEo9AAAAwQD+Z0r68c2YMNpsmyj3ZKtZNPSvJNcLmyD/
59 # lWoNjQ3djJN4s2JbK815ARUdW3xSFEDI9yx/wpfsXoaqWnygP3PoFw2CM4i0EiJiyvrLFU
60 # r3JLdUFry3EJ24RsqbigmEsgQOzTl3xfzeFPfxFoOhokSvTG88PQji1AYH5kA7p6Zfz
61 # Ok1lrJYIe7+e9B0lhku0AFwGyqlWQmS/MhIpnjHIk5tP4heHGSzmKQWJDbTskNwd6aq1G7
62 # 6HWfDpX4HgoM8AAAAALaG9sbWfuYkBhcmM=
63 # -----END OPENSSH PRIVATE KEY-----
64 #

```

2.9.8 Configure Instance to be An Ansible Controller

```

1 #cloud-config
2 #
3 # Demonstrate setting up an ansible controller host on boot.
4 # This example installs a playbook repository from a remote private repository
5 # and then runs two of the plays.
6
7 packages_update: true
8 packages_upgrade: true
9 packages:

```

(continues on next page)

(continued from previous page)

```

10  - git
11  - python3-pip
12
13  # Set up an ansible user
14  # -----
15  # In this case I give the local ansible user passwordless sudo so that ansible
16  # may write to a local root-only file.
17  users:
18  - name: ansible
19    gecos: Ansible User
20    shell: /bin/bash
21    groups: users,admin,wheel,lxd
22    sudo: ALL=(ALL) NOPASSWD:ALL
23
24  # Initialize lxd using cloud-init.
25  # -----
26  # In this example, a lxd container is
27  # started using ansible on boot, so having lxd initialized is required.
28  lxd:
29    init:
30      storage_backend: dir
31
32  # Configure and run ansible on boot
33  # -----
34  # Install ansible using pip, ensure that community.general collection is
35  # installed [1].
36  # Use a deploy key to clone a remote private repository then run two playbooks.
37  # The first playbook starts a lxd container and creates a new inventory file.
38  # The second playbook connects to and configures the container using ansible.
39  # The public version of the playbooks can be inspected here [2]
40  #
41  # [1] community.general is likely already installed by pip
42  # [2] https://github.com/holmanb/ansible-lxd-public
43  #
44  ansible:
45    install_method: pip
46    package_name: ansible
47    run_user: ansible
48    galaxy:
49      actions:
50        - ["ansible-galaxy", "collection", "install", "community.general"]
51
52  setup_controller:
53    repositories:
54      - path: /home/ansible/my-repo/
55        source: git@github.com:holmanb/ansible-lxd-private.git
56    run_ansible:
57      - playbook_dir: /home/ansible/my-repo
58        playbook_name: start-lxd.yml
59        timeout: 120
60        forks: 1
61        private_key: /home/ansible/.ssh/id_rsa

```

(continues on next page)

(continued from previous page)

```

62 - playbook_dir: /home/ansible/my-repo
63   playbook_name: configure-lxd.yml
64   become_user: ansible
65   timeout: 120
66   forks: 1
67   private_key: /home/ansible/.ssh/id_rsa
68   inventory: new_ansible_hosts
69
70 # Write a deploy key to the filesystem for ansible.
71 # -----
72 # This deploy key is tied to a private github repository [1]
73 # This key exists to demonstrate deploy key usage in ansible
74 # a duplicate public copy of the repository exists here[2]
75 #
76 # [1] https://github.com/holmanb/ansible-lxd-private
77 # [2] https://github.com/holmanb/ansible-lxd-public
78 #
79 write_files:
80 - path: /home/ansible/.ssh/known_hosts
81   owner: ansible:ansible
82   permissions: 0o600
83   defer: true
84   content: |
85     |1|YJEFak6JjnXpUjUSLfiBQS55W9E=|OLNePOn3eBa1PWhBBmt5kXsbGM4= ssh-ed25519
86     ↳ AAAAC3NzaC1lZDI1NTE5AAAAIOMqqnkVzrm0SdG6U0oqKLSabgH5C9okWi0dh2l9GKJl
87     |1|PGGnpCpqi0aakERS4BwnYxMkMwM=|Td0piZoS4ZVC00zeuRwKcH1MusM= ssh-rsa
88     ↳ AAAAB3NzaC1yc2EAAAABIwAAAEAAQ2A7hRGmdnm9tUDb09IDSwBK6TbQa+PXYPCPy6rbTrTtw7PHkccKrpp0yVhp5HdEIcKr6pLlV
89     ↳ yMf+Se8xhHTvKSCZIFImWwoG6mbUoWf9nzpIoaSjB+weqqUUpaaasXVal72J+UX2B+2RPW3RcT0eOzQgqlJL3RKRtJvdsjE3JEAv
90     ↳ w4yCE6gbODqnTWlg7+wC604ydGXA8VJiS5ap43JXiUFFAaQ==
91     |1|OJ89KrsNcFT0voCP/fPGKpyUYFo=|cu7mNzF+QB/5kR0spiYmUJL7DAI= ecdsa-sha2-nistp256
92     ↳ AAAAE2VjZHNhLXNoYTItbmlzdHAyNTYAAAAIbmlzdHAyNTYAAABBBEmKSENjQEezOmxkZMy7opKgwFB9nkt5YRrYMjNuG5N87uRgg
93     ↳ y6v0mKV0U2w0WZ2YB/++TpoCKg=
94
95 - path: /home/ansible/.ssh/id_rsa
96   owner: ansible:ansible
97   permissions: 0o600
98   defer: true
99   encoding: base64
100  content: |
101    LS0tLS1CRUdJTiBPUeVOU1NIIFBSSVZBVEUgS0VZLS0tLS0KYjNCbGJuTnphQzFyWlhrdGRqRUFb
102    QUFBQkc1dmJtVUFBUFFYm05dVpRQUFBQUFBQUFBQkFBQUJsd0FBQUFkemMyZ3RjbGpOaEFBQUFB
103    d0VBQVFBQUFZRUeWUwLlRa05WQS9VTEpWZzBzT1Q4TEwyMnRGckg5YVR1SWFNT1FiVfDtWjlnUzJh
104    VTZ0cDZoClJDYk1WSkhmOHdsaGV3MXNvWmphaWVWVSFBsUHNISm5UVlhJTnFTTlpEOGF0Rldjd1gy
105    ZTNBOElZNEhpN0NMMDE3MVBoMVUKYmJGNGVIT1JaVky2VVKzLzhmbXQ3NmhVYnpiRVhkUXhQdVdh
106    a0IyemxXNTdfClp0ejJhYVdnY2pJUGdHV1RNZWNvbEpOcQpXUW9MNlFzSSStpeUlzYXNMc1RTajha
107    aVgrT1VjanJEMUY4QXNKS3ZWQStKbnVZNUxFeno1TGQ2SGxGc05XVWtoZkNmOWVOC1pxRnJcC1Vw
108    M2VUY1FtejFGaHFFWDJlQjNQT3VSTzlkemVGcTJaRE8wU1NQ09acjBMym8vSFVTK3V5VkJNTDNI
109    eEF6eElKQWm5dFjWZjRqcTJuRjNkcUpwVTFfaXZzR0sxaHJZc0VNQk1LK0srVzRwc1F5c3ZTL0ZK
110    V2lXZmpqWVMwei9IbkV4MkpHbApOUXUrYkMxLldXSGVXTGFvNGpSckRSZnNlVnVscTE2MElsbnNx
111    eGl1MmNHd081V29Fc1NHdThucXB5ZzZzWkhDYjBGd21CCml6UFFEQVNSbmlXanFjS21mb1RycHhB
112    eTNlVldhd3dsTnBhUWtpZFRBQUFGZ0dLU2o4ZGlrby9lQUFBQUJzTnphQzF5YzIKRUFBUdCU5F
113    SWtKRFRZRUdFDeVZTZkxYay9DeTl0clJheC9XazdpR2pEa0cwMXBtZlRFdG1sT3JhZW9VUW15RlNS

```

(continues on next page)

(continued from previous page)

```

My9NSgpZWHNOYktHWTJtRkR4ejVUN0J5WjAxVnLEYWtqV1EvR3JSVm5NRjludHdQQ0dPQJR1d2k5
TmU5VDRkVkcyeGVIAHprV1ZScmVsR04vL0g1cmUrb1ZHODJ4RjNVTQ3bG1wQWRzNVZ1ZXhLMlRj
OW1tbG9ISXlENEJsa3pIbm81U1RhbGtLQytrTENQb3MKaUxHckM3RTBvL0dZbC9qbEhJNnc5UmZB
TENTcjFRUGlaN21PU3hNOCtTM2VoNVJiRFZsSk1Yd1gvWGPXYWhhd2JGS2QzawozRUZpOVJZYWhG
OWh3ZHp6cmtUdlNjM2hhdG1RenRFVWorem1hOUMyNlB4MUV2cnNsUVRD0TI4UU03UVFIUGJVlgr
STZ0CnB4ZDNhaWFWTLJJcjdCaXRZYTJMQkRBU0N2aXZsdUtiRU1yTDB2eFNWb2xuNDQyRXRNL3g1
eE1kaVJwVVFVdm13dGYxbGgKM2xpMnFPSTBhdzBYN0IXYnBhdGV0Q0paN0tzWXJ0bkJzRHVWCUJM
RWhydko2cWNvT04yUndtOUJjSmZc3owQXdfCf00bApvNm5DcG41MDY2Y3dNdDNsVm1zTUuUYVdr
SkluVXdBQUFBTUJBQUVBQUFHQUV1ejc3SHU5RUvAeXVqTE9kVG5BVzlhZlJ2ClhET1pBNnBTN3lX
RXVmcanc1Q1NsTUx3aXNSODN5d3cwOXQxUVd5dmhScUV5WW12T0JlY3NYZ2FTVXRuWmZmdF6NDRh
cHkKL2dRWXZNVkVMR0thSkFDL3E3dmpNcEd5cnhVUGt5TE1oY2tBTFUyS1lnVisvcmovajZwQk1l
VmxjaG1rM3BpallyZmZVWApKRfK50TBXV8k8xOTREbTbidUxSekp2Zk1LWUYyQmNmRjRUdmFyak9Y
V0F4U3VS0Hd3dzA1MG9KOEhkS2FoVzdDbTVTMHBvCkZSbk5YRkdNbKxBNjJ2TjAwdkpXOFY3ajd2
dWk5dWtCYmhqUlDhSnVZNXJkRy9VWW16QUW0d3ZkSUVucGs5eEluNkpHQ3AKRlJZVFJuN2xUaDUr
L1F5UTZGWFJQOElyMXZYWkZuaEt6bDBLOFZxaDZzZjRNNzlnN0lVR0F3R3hnOXhkaGpJYTVkbWdw
OApOMThJRURvTkVWS1ViS3VLZS9aNXlmoFo5dG1leGZIMVl0dGptWE1Pb2pCd1VISWpSUzVoZEK5
TnhuUEdSTfky2pBemNtCmdW0VJ2M3Z0ZEYvK3phbGszZkFWTGVLOGhYSytkaS83WFR2WXBmSjJF
WkJXaU5yVGvhZ2Z0TkdPwXlkc1F5M3pqWkFBQUEKd0JOUmFrN1VycW5JSE1abjdwa0NUZ2N1YjFN
Zk15YUZ0bE56ZCtPYmFoNTRIWU1RajVXZFpUqkFJVFJlTVp0dDlTNU5BUgpnOHNRQjhVb1pQYVZT
QzNwcElMSU9mTGhzNktZajZSckdkaVl3eUloTVBKNWtSV0Y4eEdDTFVYNUNqd0gyRU9xN1hoSVd0
Ck13RUZ0ZC9nrJjEdTdIVU5GUHNaR256SjNlN3BES0RuRTd3MmtOWjhDSXBURmdENzY5dUJZR0F0
azQ1UVlURG81SnJvVk0KWlBEcTA4R2IvUmhJJZ0pMbUlWtX5cmVWcExMTGU4U3dvTUppK3JpaG1u
Slp4T2hnQUFBTUUBMGxoaUtleMvUc2hodDR4dQpyV2MwTnh4RDg0YTI5Z1NHZlRwaERQT3JsS1NF
WWJrU1hoanFdc0FaSGQ4UzhrTXIzaUY2cG9PazNjV1N2Rko2bWJkM2llCnFkUlRnWEg5VGh3azRL
Z3BqVWh0c1F1WVJIQmJJNTlNbytCeFNJMUlxcXptSlNHZG1DQkw1NHd3elptRktEUVBRS1B4aUwK
bjBNbGM3R29vaURNalQxdGJ1Vy9PMUVMNUVxVFJxd2dXUFRLaEJBNNI0UG5HRJE1MGhaUklNb29a
a0QyeIg2YjFzR29qawpRcHZLa0V5a1R3bktDekY1VFhPOCt3SjN1YmNFbz1BQUFBd1FEK1owcjY4
YzJZTU5wc215ajNaS3RaTlBTdkp0Y0xteUQvCmxXb05KcTNkakpONHMySmJLOGw1QVJVFzceFNG
RURJOXl4L3dwZnNYb2F5V25Z1AzUG9GdzJDTTRpMEVpSml5dnJMRlUKcjNKTGZEVUZSeTNFSjI0
UnNxYmlnbUVzZ1FPelRSM3hmemVGUGZ4Rm9PaG9rU3ZURzg4UFFqaTFBWUh6NWtBN3A2WmZhegpP
azExckpZSWU3K2U5QjBsaGt1MEFGd0d5cWwXUW1TL01oSBuakhJazV0UDRoZUhuHU216S1FXSkRi
VHNrTldkNmFxmUc3CjZIV2ZEcFg0SGdvTThBQUFBTGFHOXNiV0Z1WWtCaGntTT0KLS0tLS1FTkQg
T1BFTlNTSCBQUklWQVRFIEtFWS0tLS0tCg==

```

2.9.9 Add primary apt repositories

```

1 #cloud-config
2
3 # Add primary apt repositories
4 #
5 # To add 3rd party repositories, see cloud-config-apt.txt or the
6 # Additional apt configuration and repositories section.
7 #
8 #
9 # Default: auto select based on cloud metadata
10 # in ec2, the default is <region>.archive.ubuntu.com
11 # apt:
12 #   primary:
13 #     - arches [default]
14 #     uri:

```

(continues on next page)

(continued from previous page)

```

15 #     use the provided mirror
16 #     search:
17 #     search the list for the first mirror.
18 #     this is currently very limited, only verifying that
19 #     the mirror is dns resolvable or an IP address
20 #
21 # if neither mirror is set (the default)
22 # then use the mirror provided by the DataSource found.
23 # In EC2, that means using <region>.ec2.archive.ubuntu.com
24 #
25 # if no mirror is provided by the DataSource, but 'search_dns' is
26 # true, then search for dns names '<distro>-mirror' in each of
27 # - fqdn of this host per cloud metadata
28 # - localdomain
29 # - no domain (which would search domains listed in /etc/resolv.conf)
30 # If there is a dns entry for <distro>-mirror, then it is assumed that there
31 # is a distro mirror at http://<distro>-mirror.<domain>/<distro>
32 #
33 # That gives the cloud provider the opportunity to set mirrors of a distro
34 # up and expose them only by creating dns entries.
35 #
36 # if none of that is found, then the default distro mirror is used
37 apt:
38     primary:
39         - arches: [default]
40           uri: http://us.archive.ubuntu.com/ubuntu/
41 # or
42 apt:
43     primary:
44         - arches: [default]
45           search:
46             - http://local-mirror.mydomain
47             - http://archive.ubuntu.com
48 # or
49 apt:
50     primary:
51         - arches: [default]
52           search_dns: True

```

2.9.10 Run commands on first boot

```

1 #cloud-config
2
3 # boot commands
4 # default: none
5 # this is very similar to runcmd, but commands run very early
6 # in the boot process, only slightly after a 'boothook' would run.
7 # bootcmd should really only be used for things that could not be
8 # done later in the boot process. bootcmd is very much like
9 # boothook, but possibly with more friendly.

```

(continues on next page)

(continued from previous page)

```

10 # - bootcmd will run on every boot
11 # - the INSTANCE_ID variable will be set to the current instance id.
12 # - you can use 'cloud-init-per' command to help only run once
13 bootcmd:
14   - echo 192.168.1.130 us.archive.ubuntu.com >> /etc/hosts
15   - [ cloud-init-per, once, mymkfs, mkfs, /dev/vdb ]

1 #cloud-config
2
3 # run commands
4 # default: none
5 # runcmd contains a list of either lists or a string
6 # each item will be executed in order at rc.local like level with
7 # output to the console
8 # - runcmd only runs during the first boot
9 # - if the item is a list, the items will be properly executed as if
10 #   passed to execve(3) (with the first arg as the command).
11 # - if the item is a string, it will be simply written to the file and
12 #   will be interpreted by 'sh'
13 #
14 # Note, that the list has to be proper yaml, so you have to quote
15 # any characters yaml would eat (':' can be problematic)
16 runcmd:
17   - [ ls, -l, / ]
18   - [ sh, -xc, "echo $(date) ': hello world!'" ]
19   - [ sh, -c, echo "=====hello world===== " ]
20   - ls -l /root
21   # Note: Don't write files to /tmp from cloud-init use /run/somedir instead.
22   # Early boot environments can race systemd-tmpfiles-clean LP: #1707222.
23   - mkdir /run/mydir
24   - [ wget, "http://slashdot.org", -O, /run/mydir/index.html ]

```

2.9.11 Install arbitrary packages

```

1 #cloud-config
2
3 # Install additional packages on first boot
4 #
5 # Default: none
6 #
7 # if packages are specified, then package_update will be set to true
8 #
9 # packages may be supplied as a single package name or as a list
10 # with the format [<package>, <version>] wherein the specific
11 # package version will be installed.
12 packages:
13   - pwgen
14   - pastebinit
15   - [libpython2.7, 2.7.3-0ubuntu3.1]

```


2.9.12 Update apt database on first boot

```

1 #cloud-config
2 # Update apt database on first boot (run 'apt-get update').
3 # Note, if packages are given, or package_upgrade is true, then
4 # update will be done independent of this setting.
5 #
6 # Default: false
7 package_update: true

```

2.9.13 Run apt or yum upgrade

```

1 #cloud-config
2
3 # Upgrade the instance on first boot
4 #
5 # Default: false
6 package_upgrade: true

```

2.9.14 Adjust mount points mounted

```

1 #cloud-config
2
3 # set up mount points
4 # 'mounts' contains a list of lists
5 # the inner list are entries for an /etc/fstab line
6 # ie : [ fs_spec, fs_file, fs_vfstype, fs_mntops, fs_freq, fs_passno ]
7 #
8 # default:
9 # mounts:
10 # - [ ephemeral0, /mnt ]
11 # - [ swap, none, swap, sw, 0, 0 ]
12 #
13 # in order to remove a previously listed mount (ie, one from defaults)
14 # list only the fs_spec. For example, to override the default, of
15 # mounting swap:
16 # - [ swap ]
17 # or
18 # - [ swap, null ]
19 #
20 # - if a device does not exist at the time, an entry will still be
21 #   written to /etc/fstab.
22 # - '/dev' can be omitted for device names that begin with: xvd, sd, hd, vd
23 # - if an entry does not have all 6 fields, they will be filled in
24 #   with values from 'mount_default_fields' below.
25 #
26 # Note, that you should set 'nofail' (see man fstab) for volumes that may not
27 # be attached at instance boot (or reboot).
28 #
29 mounts:

```

(continues on next page)

(continued from previous page)

```

30 - [ ephemeral0, /mnt, auto, "defaults,noexec" ]
31 - [ sdc, /opt/data ]
32 - [ xvdh, /opt/data, "auto", "defaults,nofail", "0", "0" ]
33 - [ dd, /dev/zero ]
34
35 # mount_default_fields
36 # These values are used to fill in any entries in 'mounts' that are not
37 # complete. This must be an array, and must have 6 fields.
38 mount_default_fields: [ None, None, "auto", "defaults,nofail", "0", "2" ]
39
40
41 # swap can also be set up by the 'mounts' module
42 # default is to not create any swap files, because 'size' is set to 0
43 swap:
44     filename: /swap.img
45     size: "auto" # or size in bytes
46     maxsize: 10485760 # size in bytes

```

2.9.15 Configure instances SSH keys

```

1 #cloud-config
2
3 # add each entry to ~/.ssh/authorized_keys for the configured user or the
4 # first user defined in the user definition directive.
5 ssh_authorized_keys:
6     - ssh-rsa AAAAB3NzaC1yc2EAAAABIwAAAGEA3FSyQwBI6Z+nCSjUUK8EEAnnkhXlukKoUPND/
    ↪ RRC1Wz2s5TCzIkd3Ou5+Cyz71X0XmazM3l5WgeErvtIwQMylT1KjNoMhoJMrJnWqQP0t5Q8zWd9qG7PB19+eiH5qV7NZ
    ↪ mykey@host
7     - ssh-rsa
    ↪ AAAAB3NzaC1yc2EAAAABIwAAAEQA3I7VUf2l5gSn5uavROsc5HRDpZdQueUq5ozemNSj8T7enqKHOEaFoU2VoPgGEWC9RyzSQVeyD
    ↪ +i1D+ey3ONkZLN+LQ714cgj8fRS4Hj29SCmXp5Kt5/82cd/VN3NtHw== smoser@brickies
8
9 # Send pre-generated SSH private keys to the server
10 # If these are present, they will be written to /etc/ssh and
11 # new random keys will not be generated
12 # in addition to 'rsa' and 'dsa' as shown below, 'ecdsa' is also supported
13 ssh_keys:
14     rsa_private: |
15         -----BEGIN RSA PRIVATE KEY-----
16         MIIBxwIBAAJhAKD0YSHy73nUgys013XsJmd4fHiFyQ+00R7VVu2iV9Qcon2LZS/x
17         1cydPZ4pQpfjEha6WxZ6o8ci/Ea/w0n+0HGpWaxlEG2Z9inNtj3pgFrYcRztfECb
18         1j6HCibZbAzYtwIBIwJg08h72WjcmvcpZ80vHSvTwAgu02TkR6mPgHsgSaKy6GJo
19         PUJnaZRWuba/HX0KGyhz19nPzLpzG5f0fYahlMJAYc13FV7K6kMBPXTRR6FxxgHEg
20         L0MPC7cdqAwOVNcPY6A7AJEA1bNaIjOzFN2sfZX0j70MhQuc4zP7r80zaGc5oy6W
21         p58hRAnCFKEvnEq2CeL3vtuZAJEAwNBHpbNsBYTRPCHM7rZuG/iBtwp8Rxhc9I5w
22         ixvzMgi+HpGLWzUIBS+P/XhekIjPAjA285rVmEP+DR255Ls65QbgYhJmTzIXQ2T9
23         luLvcmFBC6l35Uc4gTgg4ALsmXLn71MCMGmpSWspEvuGINayTCL+vEjmNBT+FA0
24         W7D4zCpI43jRS9U06JV0eSc9CDk2lwiA3wIwCTB/6uc8Cq85D9YqpM10FuHjKpnP
25         REPP0yrAspde0AV+6VKRavstea7+2DZmSUgE
26         -----END RSA PRIVATE KEY-----

```

(continues on next page)

(continued from previous page)

```

27  rsa_public: ssh-rsa
28  ↪ AAAAB3NzaC1yc2EAAAABIwAAAGEAoPRhIfLvedSDKw7XdewmZ3h8eIXJD7TRHtVW7aJX1ByiFYt1L/
↪ HVzJ09nilCl+MSFrpbFnqjxyl8Rr/DSf7QcY/BrGUQbZn2Kc22PemAWthxH018QJvWPocKJt1sDNi3
↪ smoser@localhost

29
30  dsa_private: |
31  -----BEGIN DSA PRIVATE KEY-----
32  MIIBuwIBAAKBgQDP2HLu7pTEXL89USyM0264RCyWX/CMLmukxX0Jdbm29ax8FBJT
33  pLr08TIXVY5rPAJmIdTHnpuyJh0vU9G7M8tPUABtzSJh4GVSHlwaCfycwcpLv9TX
34  DgWIpSj+6EiHCyaRlB1/CBp9RiaB+10QcFbm+lapuET+/Au6vSDp9IRtlQIVAIMR
35  8KucvUYbOEI+yv+5LW9u3z/BAoGBAI0q6JP+JvJmwZFaeCMMVxXUbqiSko/P1lsa
36  LNNBHZ5/8MOUIm8rB2FC6ziidfueJpqTMqeQmSAlEBCwnwreUnGfRrKoJpyPNENY
37  d15MG6N5J+z81sEcHFeprryZ+D3Ge9VjPq3Tf3NhKKwCDQ0240aPezbnjPeFm4mH
38  bYxxcZ9GAoGAXmLIFSQgiAPu459rCKxT46tHJtMQQfnNiEnQLbFluefZ/yiI4DI3
39  8UzTCOXLhUA7ybmZha+D/csj15Y9/BNFu07unzVhikCQV9DTeXX46pG4s1o23JKC
40  /QaYWNMZ7kTRv+wWow9MhGiVdML4ZN4Xnifu05krqAybngIy66PMEoQCFEIsKKWv
41  99iziAH0KBMVbxy03Trz
42  -----END DSA PRIVATE KEY-----

43
44  dsa_public: ssh-dss AAAAB3NzaC1kc3MAAACBAM/
↪ Ycu7ulMTEvz1RLIzTbrhELJZf8Iwua6TFfQ1lubb1rHwUEl0kus7xMhdVjms8AmbV1Meem7ImE69T0bszy09QAG3NImHgZVieXBoJ
↪ JzByku/
↪ 1Nc0BYilKP7oSiC1JpGUHX8IGn1GJoH7XRBwVub6Vqm4RP78C7q9I0n0hG2VAAAAFQCDEfCrnL1GGzhCPsr/
↪ uS1vbt8/wQAAAIEAjSrok/4m8mbBkVp4IwxXFdRuqJKSj8/WWxos00Ednn/
↪ ww5QibysHYULrOKJ1+54mmpMyp5CZICUQELCfCt5ScZ9GsqqmnI80Q1h3Xkwbo3kn7PzWwRwcV6muvJn4PcZ71WM+rdN/
↪ c2EorAINDTbjRo97NueM94WbiYdtjHFxn0YAAACAXmLIFSQgiAPu459rCKxT46tHJtMQQfnNiEnQLbFluefZ/
↪ yiI4DI38UzTCOXLhUA7ybmZha+D/csj15Y9/BNFu07unzVhikCQV9DTeXX46pG4s1o23JKC/
↪ QaYWNMZ7kTRv+wWow9MhGiVdML4ZN4Xnifu05krqAybngIy66PMEoQ= smoser@localhost

45
46  # By default, the fingerprints of the authorized keys for the users
47  # cloud-init adds are printed to the console. Setting
48  # no_ssh_fingerprints to true suppresses this output.
49  no_ssh_fingerprints: false

50
51  # By default, (most) ssh host keys are printed to the console. Setting
52  # emit_keys_to_console to false suppresses this output.
53  ssh:
54  emit_keys_to_console: false

```

2.9.16 Additional apt configuration and repositories

```

1  #cloud-config
2  # apt_pipelining (configure Acquire::http::Pipeline-Depth)
3  # Default: disables HTTP pipelining. Certain web servers, such
4  # as S3 do not pipeline properly (LP: #948461).
5  # Valid options:
6  #   False/default: Disables pipelining for APT
7  #   None/Unchanged: Use OS default
8  #   Number: Set pipelining to some number (not recommended)

```

(continues on next page)

(continued from previous page)

```

9 apt_pipelining: False
10
11 ## apt config via system_info:
12 # under the 'system_info', you can customize cloud-init's interaction
13 # with apt.
14 # system_info:
15 # apt_get_command: [command, argument, argument]
16 # apt_get_upgrade_subcommand: dist-upgrade
17 #
18 # apt_get_command:
19 # To specify a different 'apt-get' command, set 'apt_get_command'.
20 # This must be a list, and the subcommand (update, upgrade) is appended to it.
21 # default is:
22 # ['apt-get', '--option=Dpkg::Options::--force-confold',
23 #  '--option=Dpkg::options::--force-unsafe-io', '--assume-yes', '--quiet']
24 #
25 # apt_get_upgrade_subcommand: "dist-upgrade"
26 # Specify a different subcommand for 'upgrade'. The default is 'dist-upgrade'.
27 # This is the subcommand that is invoked for package_upgrade.
28 #
29 # apt_get_wrapper:
30 # command: eatmydata
31 # enabled: [True, False, "auto"]
32 #
33
34 # Install additional packages on first boot
35 #
36 # Default: none
37 #
38 # if packages are specified, then package_update will be set to true
39
40 packages: ['pastebinit']
41
42 apt:
43 # The apt config consists of two major "areas".
44 #
45 # On one hand there is the global configuration for the apt feature.
46 #
47 # On one hand (down in this file) there is the source dictionary which allows
48 # to define various entries to be considered by apt.
49
50 #####
51 # Section 1: global apt configuration
52 #
53 # The following examples number the top keys to ease identification in
54 # discussions.
55
56 # 1.1 preserve_sources_list
57 #
58 # Preserves the existing /etc/apt/sources.list
59 # Default: false - do overwrite sources_list. If set to true then any
60 # "mirrors" configuration will have no effect.

```

(continues on next page)

(continued from previous page)

```

61 # Set to true to avoid affecting sources.list. In that case only
62 # "extra" source specifications will be written into
63 # /etc/apt/sources.list.d/*
64 preserve_sources_list: true
65
66 # 1.2 disable_suites
67 #
68 # This is an empty list by default, so nothing is disabled.
69 #
70 # If given, those suites are removed from sources.list after all other
71 # modifications have been made.
72 # Suites are even disabled if no other modification was made,
73 # but not if is preserve_sources_list is active.
74 # There is a special alias "$RELEASE" as in the sources that will be replace
75 # by the matching release.
76 #
77 # To ease configuration and improve readability the following common ubuntu
78 # suites will be automatically mapped to their full definition.
79 # updates    => $RELEASE-updates
80 # backports  => $RELEASE-backports
81 # security   => $RELEASE-security
82 # proposed   => $RELEASE-proposed
83 # release    => $RELEASE
84 #
85 # There is no harm in specifying a suite to be disabled that is not found in
86 # the source.list file (just a no-op then)
87 #
88 # Note: Lines don't get deleted, but disabled by being converted to a comment.
89 # The following example disables all usual defaults except $RELEASE-security.
90 # On top it disables a custom suite called "mysuite"
91 disable_suites: [$RELEASE-updates, backports, $RELEASE, mysuite]
92
93 # 1.3 primary/security archives
94 #
95 # Default: none - instead it is auto select based on cloud metadata
96 # so if neither "uri" nor "search", nor "search_dns" is set (the default)
97 # then use the mirror provided by the DataSource found.
98 # In EC2, that means using <region>.ec2.archive.ubuntu.com
99 #
100 # define a custom (e.g. localized) mirror that will be used in sources.list
101 # and any custom sources entries for deb / deb-src lines.
102 #
103 # One can set primary and security mirror to different uri's
104 # the child elements to the keys primary and secondary are equivalent
105 primary:
106 # arches is list of architectures the following config applies to
107 # the special keyword "default" applies to any architecture not explicitly
108 # listed.
109 - arches: [amd64, i386, default]
110 # uri is just defining the target as-is
111 uri: http://us.archive.ubuntu.com/ubuntu
112 #

```

(continues on next page)

(continued from previous page)

```

113 # via search one can define lists that are tried one by one.
114 # The first with a working DNS resolution (or if it is an IP) will be
115 # picked. That way one can keep one configuration for multiple
116 # subenvironments that select the working one.
117 search:
118     - http://cool.but-sometimes-unreachable.com/ubuntu
119     - http://us.archive.ubuntu.com/ubuntu
120 # if no mirror is provided by uri or search but 'search_dns' is
121 # true, then search for dns names '<distro>-mirror' in each of
122 # - fqdn of this host per cloud metadata
123 # - localdomain
124 # - no domain (which would search domains listed in /etc/resolv.conf)
125 # If there is a dns entry for <distro>-mirror, then it is assumed that
126 # there is a distro mirror at http://<distro>-mirror.<domain>/<distro>
127 #
128 # That gives the cloud provider the opportunity to set mirrors of a distro
129 # up and expose them only by creating dns entries.
130 #
131 # if none of that is found, then the default distro mirror is used
132 search_dns: true
133 #
134 # If multiple of a category are given
135 # 1. uri
136 # 2. search
137 # 3. search_dns
138 # the first defining a valid mirror wins (in the order as defined here,
139 # not the order as listed in the config).
140 #
141 # Additionally, if the repository requires a custom signing key, it can be
142 # specified via the same fields as for custom sources:
143 # 'keyid': providing a key to import via shortid or fingerprint
144 # 'key': providing a raw PGP key
145 # 'keyserver': specify an alternate keyserver to pull keys from that
146 #               were specified by keyid
147 - arches: [s390x, arm64]
148 # as above, allowing to have one config for different per arch mirrors
149 # security is optional, if not defined it is set to the same value as primary
150 security:
151     - uri: http://security.ubuntu.com/ubuntu
152       arches: [default]
153 # If search_dns is set for security the searched pattern is:
154 # <distro>-security-mirror
155
156 # if no mirrors are specified at all, or all lookups fail it will try
157 # to get them from the cloud datasource and if those neither provide one fall
158 # back to:
159 # primary: http://archive.ubuntu.com/ubuntu
160 # security: http://security.ubuntu.com/ubuntu
161
162 # 1.4 sources_list
163 #
164 # Provide a custom template for rendering sources.list

```

(continues on next page)

(continued from previous page)

```

165 # without one provided cloud-init uses builtin templates for
166 # ubuntu and debian.
167 # Within these sources.list templates you can use the following replacement
168 # variables (all have sane Ubuntu defaults, but mirrors can be overwritten
169 # as needed (see above)):
170 # => $RELEASE, $MIRROR, $PRIMARY, $SECURITY
171 sources_list: | # written by cloud-init custom template
172     deb $MIRROR $RELEASE main restricted
173     deb-src $MIRROR $RELEASE main restricted
174     deb $PRIMARY $RELEASE universe restricted
175     deb $SECURITY $RELEASE-security multiverse
176
177 # 1.5 conf
178 #
179 # Any apt config string that will be made available to apt
180 # see the APT.CONF(5) man page for details what can be specified
181 conf: | # APT config
182     APT {
183         Get {
184             Assume-Yes "true";
185             Fix-Broken "true";
186         };
187     };
188
189 # 1.6 (http_/ftp_/https_)proxy
190 #
191 # Proxies are the most common apt.conf option, so that for simplified use
192 # there is a shortcut for those. Those get automatically translated into the
193 # correct Acquire::*::Proxy statements.
194 #
195 # note: proxy actually being a short synonym to http_proxy
196 proxy: http://[[user][:pass]@]host[:port]/
197 http_proxy: http://[[user][:pass]@]host[:port]/
198 ftp_proxy: ftp://[[user][:pass]@]host[:port]/
199 https_proxy: https://[[user][:pass]@]host[:port]/
200
201 # 1.7 add_apt_repo_match
202 #
203 # 'source' entries in apt-sources that match this python regex
204 # expression will be passed to add-apt-repository
205 # The following example is also the builtin default if nothing is specified
206 add_apt_repo_match: '^[\\w-]+:\\w'
207
208 #####
209 # Section 2: source list entries
210 #
211 # This is a dictionary (unlike most block/net which are lists)
212 #
213 # The key of each source entry is the filename and will be prepended by
214 # /etc/apt/sources.list.d/ if it doesn't start with a '/'.
215 # If it doesn't end with .list it will be appended so that apt picks up its

```

(continues on next page)

(continued from previous page)

```

217 # configuration.
218 #
219 # Whenever there is no content to be written into such a file, the key is
220 # not used as filename - yet it can still be used as index for merging
221 # configuration.
222 #
223 # The values inside the entries consist of the following optional entries:
224 # 'source': a sources.list entry (some variable replacements apply)
225 # 'keyid': providing a key to import via shortid or fingerprint
226 # 'key': providing a raw PGP key
227 # 'keyserver': specify an alternate keyserver to pull keys from that
228 #               were specified by keyid
229
230 # This allows merging between multiple input files than a list like:
231 # cloud-config1
232 # sources:
233 #   s1: {'key': 'key1', 'source': 'source1'}
234 # cloud-config2
235 # sources:
236 #   s2: {'key': 'key2'}
237 #   s1: {'keyserver': 'foo'}
238 # This would be merged to
239 # sources:
240 #   s1:
241 #     keyserver: foo
242 #     key: key1
243 #     source: source1
244 #   s2:
245 #     key: key2
246 #
247 # The following examples number the subfeatures per sources entry to ease
248 # identification in discussions.
249
250
251 sources:
252   curtin-dev-ppa.list:
253     # 2.1 source
254     #
255     # Creates a file in /etc/apt/sources.list.d/ for the sources list entry
256     # based on the key: "/etc/apt/sources.list.d/curtin-dev-ppa.list"
257     source: "deb http://ppa.launchpad.net/curtin-dev/test-archive/ubuntu bionic main"
258
259     # 2.2 keyid
260     #
261     # Importing a gpg key for a given key id. Used keyserver defaults to
262     # keyserver.ubuntu.com
263     keyid: F430BBA5 # GPG key ID published on a key server
264
265   ignored1:
266     # 2.3 PPA shortcut
267     #
268     # Setup correct apt sources.list line and Auto-Import the signing key

```

(continues on next page)

(continued from previous page)

```

269 # from LP
270 #
271 # See https://help.launchpad.net/Packaging/PPA for more information
272 # this requires 'add-apt-repository'. This will create a file in
273 # /etc/apt/sources.list.d automatically, therefore the key here is
274 # ignored as filename in those cases.
275 source: "ppa:curtin-dev/test-archive"    # Quote the string
276
277 my-repo2.list:
278 # 2.4 replacement variables
279 #
280 # sources can use $MIRROR, $PRIMARY, $SECURITY, $RELEASE and $KEY_FILE
281 # replacement variables.
282 # They will be replaced with the default or specified mirrors and the
283 # running release.
284 # The entry below would be possibly turned into:
285 # source: deb http://archive.ubuntu.com/ubuntu bionic multiverse
286 source: deb [signed-by=$KEY_FILE] $MIRROR $RELEASE multiverse
287 keyid: F430BBA5
288
289 my-repo3.list:
290 # this would have the same end effect as 'ppa:curtin-dev/test-archive'
291 source: "deb http://ppa.launchpad.net/curtin-dev/test-archive/ubuntu bionic main"
292 keyid: F430BBA5 # GPG key ID published on the key server
293 filename: curtin-dev-ppa.list
294
295 ignored2:
296 # 2.5 key only
297 #
298 # this would only import the key without adding a ppa or other source spec
299 # since this doesn't generate a source.list file the filename key is ignored
300 keyid: F430BBA5 # GPG key ID published on a key server
301
302 ignored3:
303 # 2.6 key id alternatives
304 #
305 # Keyid's can also be specified via their long fingerprints
306 keyid: B59D 5F15 97A5 04B7 E230 6DCA 0620 BBCF 0368 3F77
307
308 ignored4:
309 # 2.7 alternative key servers
310 #
311 # One can also specify alternative key servers to fetch keys from.
312 keyid: B59D 5F15 97A5 04B7 E230 6DCA 0620 BBCF 0368 3F77
313 keyserver: pgp.mit.edu
314
315 ignored5:
316 # 2.8 signed-by
317 #
318 # One can specify [signed-by=$KEY_FILE] in the source definition, which
319 # will make the key be installed in the directory /etc/cloud-init.gpg.d/
320 # and the $KEY_FILE replacement variable will be replaced with the path

```

(continues on next page)

(continued from previous page)

```

321 # to the specified key. If $KEY_FILE is used, but no key is specified,
322 # apt update will (rightfully) fail due to an invalid value.
323 source: deb [signed-by=$KEY_FILE] $MIRROR $RELEASE multiverse
324 keyid: B59D 5F15 97A5 04B7 E230 6DCA 0620 BBCF 0368 3F77
325
326 my-repo4.list:
327 # 2.9 raw key
328 #
329 # The apt signing key can also be specified by providing a pgp public key
330 # block. Providing the PGP key this way is the most robust method for
331 # specifying a key, as it removes dependency on a remote key server.
332 #
333 # As with keyid's this can be specified with or without some actual source
334 # content.
335 key: | # The value needs to start with -----BEGIN PGP PUBLIC KEY BLOCK-----
336 -----BEGIN PGP PUBLIC KEY BLOCK-----
337 Version: SKS 1.0.10
338
339 mI0ESpA3UQEEALdZKVMq0j6qWAXAyxSlF63SvPVIgxHPb9Nk0DZUixn+akqytxG4zKCONz6
340 qLjoBBfHnynyVLfT4ihg9an1PqxRnTO+JKQx18NgKGz6Pon569GtA0dWNKw15XKinJTDLjnj
341 9y96ljJqRcpV9t/WsIcdJPcKFR5voHTEoABE2aEXABEBAAG0GUxhdW5jaHBhZCBQUEEgZm9y
342 IEFsZXN0aW0ItgQTAQIAIAUCSpA3UQIbAwYLCQgHAWIEFQIIAwQWAgMBAh4BAheAAAJEA7H
343 5Qi+CcVxWZ8D/1MyYvfj3FJPZUm2Yo1zZsQ657vHI9+pPouqflW0ayRR9jbiyUFIn0VdQBrP
344 t0FwvnOFarUovUWoKAEdqR8hPy3M3APUZjl5K4cMZR/xaMQeQRZ5CHpS4DBKURKAHC0ltS5o
345 uBJKQ0Zm5iltJp15cgyIkBkGe8Mx18VFyVglAZey
346 =Y2oI
347 -----END PGP PUBLIC KEY BLOCK-----

```

2.9.17 Disk setup

```

1 #cloud-config
2 # Cloud-init supports the creation of simple partition tables and file systems
3 # on devices.
4
5 # Default disk definitions for AWS
6 # -----
7 # (Not implemented yet, but provided for future documentation)
8
9 disk_setup:
10 ephemeral0:
11   table_type: 'mbr'
12   layout: True
13   overwrite: False
14
15 fs_setup:
16 - label: None,
17   filesystem: ext3
18   device: ephemeral0
19   partition: auto
20

```

(continues on next page)

(continued from previous page)

```

21 # Default disk definitions for Microsoft Azure
22 # -----
23
24 device_aliases: {'ephemeral0': '/dev/sdb'}
25 disk_setup:
26     ephemeral0:
27         table_type: mbr
28         layout: True
29         overwrite: False
30
31 fs_setup:
32     - label: ephemeral0
33       filesystem: ext4
34       device: ephemeral0.1
35       replace_fs: ntfs
36
37
38 # Data disks definitions for Microsoft Azure
39 # -----
40
41 disk_setup:
42     /dev/disk/azure/scsi1/lun0:
43         table_type: gpt
44         layout: True
45         overwrite: True
46
47 fs_setup:
48     - device: /dev/disk/azure/scsi1/lun0
49       partition: 1
50       filesystem: ext4
51
52
53 # Default disk definitions for SmartOS
54 # -----
55
56 device_aliases: {'ephemeral0': '/dev/vdb'}
57 disk_setup:
58     ephemeral0:
59         table_type: mbr
60         layout: False
61         overwrite: False
62
63 fs_setup:
64     - label: ephemeral0
65       filesystem: ext4
66       device: ephemeral0.0
67
68 # Caveat for SmartOS: if ephemeral disk is not defined, then the disk will
69 #   not be automatically added to the mounts.
70
71
72 # The default definition is used to make sure that the ephemeral storage is

```

(continues on next page)

(continued from previous page)

```

73 # setup properly.
74
75 # "disk_setup": disk partitioning
76 # -----
77
78 # The disk_setup directive instructs Cloud-init to partition a disk. The format is:
79
80 disk_setup:
81     ephemeral0:
82         table_type: 'mbr'
83         layout: true
84     /dev/xvda:
85         table_type: 'mbr'
86         layout:
87             - 33
88             - [33, 82]
89             - 33
90         overwrite: True
91
92 # The format is a list of dicts of dicts. The first value is the name of the
93 # device and the subsequent values define how to create and layout the
94 # partition.
95 # The general format is:
96 #   disk_setup:
97 #       <DEVICE>:
98 #           table_type: 'mbr'
99 #           layout: <LAYOUT/BOOL>
100 #           overwrite: <BOOL>
101 #
102 # Where:
103 #   <DEVICE>: The name of the device. 'ephemeralX' and 'swap' are special
104 #             values which are specific to the cloud. For these devices
105 #             Cloud-init will look up what the real devices is and then
106 #             use it.
107 #
108 #             For other devices, the kernel device name is used. At this
109 #             time only simply kernel devices are supported, meaning
110 #             that device mapper and other targets may not work.
111 #
112 #             Note: At this time, there is no handling or setup of
113 #             device mapper targets.
114 #
115 #   table_type=<TYPE>: Currently the following are supported:
116 #                       'mbr': default and setups a MS-DOS partition table
117 #                       'gpt': setups a GPT partition table
118 #
119 #             Note: At this time only 'mbr' and 'gpt' partition tables
120 #             are allowed. It is anticipated in the future that
121 #             we'll also have "RAID" to create a mdadm RAID.
122 #
123 #   layout={...}: The device layout. This is a list of values, with the
124 #                 percentage of disk that partition will take.

```

(continues on next page)

(continued from previous page)

```

125 # Valid options are:
126 #     [<SIZE>, [<SIZE>, <PART_TYPE>]]
127 #
128 # Where <SIZE> is the _percentage_ of the disk to use, while
129 # <PART_TYPE> is the numerical value of the partition type.
130 #
131 # The following setups two partitions, with the first
132 # partition having a swap label, taking 1/3 of the disk space
133 # and the remainder being used as the second partition.
134 # /dev/xvdh':
135 #     table_type: 'mbr'
136 #     layout:
137 #         - [33,82]
138 #         - 66
139 #     overwrite: True
140 #
141 # When layout is "true" it means single partition the entire
142 # device.
143 #
144 # When layout is "false" it means don't partition or ignore
145 # existing partitioning.
146 #
147 # If layout is set to "true" and overwrite is set to "false",
148 # it will skip partitioning the device without a failure.
149 #
150 # overwrite=<BOOL>: This describes whether to ride with saftey's on and
151 # everything holstered.
152 #
153 # 'false' is the default, which means that:
154 #     1. The device will be checked for a partition table
155 #     2. The device will be checked for a file system
156 #     3. If either a partition of file system is found, then
157 #        the operation will be _skipped_.
158 #
159 # 'true' is cowboy mode. There are no checks and things are
160 # done blindly. USE with caution, you can do things you
161 # really, really don't want to do.
162 #
163 #
164 # fs_setup: Setup the file system
165 # -----
166 #
167 # fs_setup describes the how the file systems are supposed to look.
168
169 fs_setup:
170 - label: ephemeral0
171   filesystem: 'ext3'
172   device: 'ephemeral0'
173   partition: 'auto'
174 - label: mylabl2
175   filesystem: 'ext4'
176   device: '/dev/xvda1'

```

(continues on next page)

(continued from previous page)

```

177 - cmd: mkfs -t %(filesystem)s -L %(label)s %(device)s
178   label: mylabl3
179   filesystem: 'btrfs'
180   device: '/dev/xvdb'
181
182 # The general format is:
183 #   fs_setup:
184 #     - label: <LABEL>
185 #       filesystem: <FS_TYPE>
186 #       device: <DEVICE>
187 #       partition: <PART_VALUE>
188 #       overwrite: <OVERWRITE>
189 #       replace_fs: <FS_TYPE>
190 #
191 # Where:
192 #   <LABEL>: The file system label to be used. If set to None, no label is
193 #   used.
194 #
195 #   <FS_TYPE>: The file system type. It is assumed that there
196 #   will be a "mkfs.<FS_TYPE>" that behaves like "mkfs". On a standard
197 #   Ubuntu Cloud Image, this means that you have the option of ext{2,3,4},
198 #   and vfat by default.
199 #
200 #   <DEVICE>: The device name. Special names of 'ephemeralX' or 'swap'
201 #   are allowed and the actual device is acquired from the cloud datasource.
202 #   When using 'ephemeralX' (i.e. ephemeral0), make sure to leave the
203 #   label as 'ephemeralX' otherwise there may be issues with the mounting
204 #   of the ephemeral storage layer.
205 #
206 #   If you define the device as 'ephemeralX.Y' then Y will be interpreted
207 #   as a partition value. However, ephemeralX.0 is the _same_ as ephemeralX.
208 #
209 #   <PART_VALUE>:
210 #   Partition definitions are overwritten if you use the '<DEVICE>.Y' notation.
211 #
212 #   The valid options are:
213 #   "auto/any": tell cloud-init not to care whether there is a partition
214 #   or not. Auto will use the first partition that does not contain a
215 #   file system already. In the absence of a partition table, it will
216 #   put it directly on the disk.
217 #
218 #   "auto": If a file system that matches the specification in terms of
219 #   label, type and device, then cloud-init will skip the creation of
220 #   the file system.
221 #
222 #   "any": If a file system that matches the file system type and device,
223 #   then cloud-init will skip the creation of the file system.
224 #
225 #   Devices are selected based on first-detected, starting with partitions
226 #   and then the raw disk. Consider the following:
227 #       NAME      FSTYPE LABEL
228 #       xvdb

```

(continues on next page)

(continued from previous page)

```

229 #         |-xvdb1  ext4
230 #         |-xvdb2
231 #         |-xvdb3  btrfs  test
232 #         \-xvdb4  ext4   test
233 #
234 #         If you ask for 'auto', label of 'test', and file system of 'ext4'
235 #         then cloud-init will select the 2nd partition, even though there
236 #         is a partition match at the 4th partition.
237 #
238 #         If you ask for 'any' and a label of 'test', then cloud-init will
239 #         select the 1st partition.
240 #
241 #         If you ask for 'auto' and don't define label, then cloud-init will
242 #         select the 1st partition.
243 #
244 #         In general, if you have a specific partition configuration in mind,
245 #         you should define either the device or the partition number. 'auto'
246 #         and 'any' are specifically intended for formatting ephemeral storage or
247 #         for simple schemes.
248 #
249 #         "none": Put the file system directly on the device.
250 #
251 #         <NUM>: where NUM is the actual partition number.
252 #
253 #         <OVERWRITE>: Defines whether or not to overwrite any existing
254 #         filesystem.
255 #
256 #         "true": Indiscriminately destroy any pre-existing file system. Use at
257 #         your own peril.
258 #
259 #         "false": If an existing file system exists, skip the creation.
260 #
261 #         <REPLACE_FS>: This is a special directive, used for Microsoft Azure that
262 #         instructs cloud-init to replace a file system of <FS_TYPE>. NOTE:
263 #         unless you define a label, this requires the use of the 'any' partition
264 #         directive.
265 #
266 # Behavior Caveat: The default behavior is to check if the file system exists.
267 # If a file system matches the specification, then the operation is a no-op.

```

2.9.18 Configure data sources

```

1 #cloud-config
2
3 # Documentation on data sources configuration options
4 datasource:
5     # Ec2
6     Ec2:
7         # timeout: the timeout value for a request at metadata service
8         timeout : 50

```

(continues on next page)

(continued from previous page)

```

9      # The length in seconds to wait before giving up on the metadata
10     # service. The actual total wait could be up to
11     # len(resolvable_metadata_urls)*timeout
12     max_wait : 120
13
14     #metadata_url: a list of URLs to check for metadata services
15     metadata_urls:
16     - http://169.254.169.254:80
17     - http://instance-data:8773
18
19     MAAS:
20     timeout : 50
21     max_wait : 120
22
23     # there are no default values for metadata_url or oauth credentials
24     # If no credentials are present, non-authed attempts will be made.
25     metadata_url: http://mass-host.localdomain/source
26     consumer_key: Xh234sdlkjljf
27     token_key: kjfhgb3n
28     token_secret: 24uysdfx1w4
29
30     NoCloud:
31     # default seedfrom is None
32     # if found, then it should contain a url with:
33     # <url>/user-data and <url>/meta-data
34     # seedfrom: http://my.example.com/i-abcde
35     seedfrom: None
36
37     # fs_label: the label on filesystems to be searched for NoCloud source
38     fs_label: cidata
39
40     # these are optional, but allow you to basically provide a datasource
41     # right here
42     user-data: |
43     # This is the user-data verbatim
44     meta-data:
45     instance-id: i-87018aed
46     local-hostname: myhost.internal
47
48     SmartOS:
49     # For KVM guests:
50     # Smart OS datasource works over a serial console interacting with
51     # a server on the other end. By default, the second serial console is the
52     # device. SmartOS also uses a serial timeout of 60 seconds.
53     serial_device: /dev/ttyS1
54     serial_timeout: 60
55
56     # For LX-Brand Zones guests:
57     # Smart OS datasource works over a socket interacting with
58     # the host on the other end. By default, the socket file is in
59     # the native .zoncontrol directory.
60     metadata_sockfile: /native/.zonecontrol/metadata.sock

```

(continues on next page)

(continued from previous page)

```

61
62     # a list of keys that will not be base64 decoded even if base64_all
63     no_base64_decode: ['root_authorized_keys', 'motd_sys_info',
64                        'iptables_disable']
65     # a plaintext, comma delimited list of keys whose values are b64 encoded
66     base64_keys: []
67     # a boolean indicating that all keys not in 'no_base64_decode' are encoded
68     base64_all: False

```

2.9.19 Create partitions and filesystems

```

1  #cloud-config
2  # Cloud-init supports the creation of simple partition tables and file systems
3  # on devices.
4
5  # Default disk definitions for AWS
6  # -----
7  # (Not implemented yet, but provided for future documentation)
8
9  disk_setup:
10     ephemeral0:
11         table_type: 'mbr'
12         layout: True
13         overwrite: False
14
15  fs_setup:
16     - label: None,
17       filesystem: ext3
18       device: ephemeral0
19       partition: auto
20
21  # Default disk definitions for Microsoft Azure
22  # -----
23
24  device_aliases: {'ephemeral0': '/dev/sdb'}
25  disk_setup:
26     ephemeral0:
27         table_type: mbr
28         layout: True
29         overwrite: False
30
31  fs_setup:
32     - label: ephemeral0
33       filesystem: ext4
34       device: ephemeral0.1
35       replace_fs: ntfs
36
37
38  # Data disks definitions for Microsoft Azure
39  # -----

```

(continues on next page)

(continued from previous page)

```

40
41 disk_setup:
42     /dev/disk/azure/scsi1/lun0:
43         table_type: gpt
44         layout: True
45         overwrite: True
46
47 fs_setup:
48     - device: /dev/disk/azure/scsi1/lun0
49       partition: 1
50       filesystem: ext4
51
52
53 # Default disk definitions for SmartOS
54 # -----
55
56 device_aliases: {'ephemeral0': '/dev/vdb'}
57 disk_setup:
58     ephemeral0:
59         table_type: mbr
60         layout: False
61         overwrite: False
62
63 fs_setup:
64     - label: ephemeral0
65       filesystem: ext4
66       device: ephemeral0.0
67
68 # Caveat for SmartOS: if ephemeral disk is not defined, then the disk will
69 #   not be automatically added to the mounts.
70
71
72 # The default definition is used to make sure that the ephemeral storage is
73 # setup properly.
74
75 # "disk_setup": disk partitioning
76 # -----
77
78 # The disk_setup directive instructs Cloud-init to partition a disk. The format is:
79
80 disk_setup:
81     ephemeral0:
82         table_type: 'mbr'
83         layout: true
84     /dev/xvdh:
85         table_type: 'mbr'
86         layout:
87             - 33
88             - [33, 82]
89             - 33
90         overwrite: True
91

```

(continues on next page)

(continued from previous page)

```

92 # The format is a list of dicts of dicts. The first value is the name of the
93 # device and the subsequent values define how to create and layout the
94 # partition.
95 # The general format is:
96 #   disk_setup:
97 #       <DEVICE>:
98 #           table_type: 'mbr'
99 #           layout: <LAYOUT/BOOL>
100 #           overwrite: <BOOL>
101 #
102 # Where:
103 #   <DEVICE>: The name of the device. 'ephemeralX' and 'swap' are special
104 #             values which are specific to the cloud. For these devices
105 #             Cloud-init will look up what the real devices is and then
106 #             use it.
107 #
108 #             For other devices, the kernel device name is used. At this
109 #             time only simply kernel devices are supported, meaning
110 #             that device mapper and other targets may not work.
111 #
112 #             Note: At this time, there is no handling or setup of
113 #             device mapper targets.
114 #
115 #   table_type=<TYPE>: Currently the following are supported:
116 #                       'mbr': default and setups a MS-DOS partition table
117 #                       'gpt': setups a GPT partition table
118 #
119 #                       Note: At this time only 'mbr' and 'gpt' partition tables
120 #                       are allowed. It is anticipated in the future that
121 #                       we'll also have "RAID" to create a mdadm RAID.
122 #
123 #   layout={...}: The device layout. This is a list of values, with the
124 #                 percentage of disk that partition will take.
125 #                 Valid options are:
126 #                 [<SIZE>, [<SIZE>, <PART_TYPE>]]
127 #
128 #                 Where <SIZE> is the _percentage_ of the disk to use, while
129 #                 <PART_TYPE> is the numerical value of the partition type.
130 #
131 #                 The following setups two partitions, with the first
132 #                 partition having a swap label, taking 1/3 of the disk space
133 #                 and the remainder being used as the second partition.
134 #                 /dev/xvdb:
135 #                     table_type: 'mbr'
136 #                     layout:
137 #                         - [33,82]
138 #                         - 66
139 #                     overwrite: True
140 #
141 #                 When layout is "true" it means single partition the entire
142 #                 device.
143 #

```

(continues on next page)

(continued from previous page)

```

144 #           When layout is "false" it means don't partition or ignore
145 #           existing partitioning.
146 #
147 #           If layout is set to "true" and overwrite is set to "false",
148 #           it will skip partitioning the device without a failure.
149 #
150 #   overwrite=<BOOL>: This describes whether to ride with saftey's on and
151 #   everything holstered.
152 #
153 #           'false' is the default, which means that:
154 #               1. The device will be checked for a partition table
155 #               2. The device will be checked for a file system
156 #               3. If either a partition of file system is found, then
157 #                  the operation will be _skipped_.
158 #
159 #           'true' is cowboy mode. There are no checks and things are
160 #           done blindly. USE with caution, you can do things you
161 #           really, really don't want to do.
162 #
163 #
164 # fs_setup: Setup the file system
165 # -----
166 #
167 # fs_setup describes the how the file systems are supposed to look.
168
169 fs_setup:
170 - label: ephemeral0
171   filesystem: 'ext3'
172   device: 'ephemeral0'
173   partition: 'auto'
174 - label: mylabl2
175   filesystem: 'ext4'
176   device: '/dev/xvda1'
177 - cmd: mkfs -t %(filesystem)s -L %(label)s %(device)s
178   label: mylabl3
179   filesystem: 'btrfs'
180   device: '/dev/xvda1'
181
182 # The general format is:
183 #   fs_setup:
184 #       - label: <LABEL>
185 #         filesystem: <FS_TYPE>
186 #         device: <DEVICE>
187 #         partition: <PART_VALUE>
188 #         overwrite: <OVERWRITE>
189 #         replace_fs: <FS_TYPE>
190 #
191 # Where:
192 #   <LABEL>: The file system label to be used. If set to None, no label is
193 #   used.
194 #
195 #   <FS_TYPE>: The file system type. It is assumed that the there

```

(continues on next page)

(continued from previous page)

```

196 # will be a "mkfs.<FS_TYPE>" that behaves likes "mkfs". On a standard
197 # Ubuntu Cloud Image, this means that you have the option of ext{2,3,4},
198 # and vfat by default.
199 #
200 # <DEVICE>: The device name. Special names of 'ephemeralX' or 'swap'
201 # are allowed and the actual device is acquired from the cloud datasource.
202 # When using 'ephemeralX' (i.e. ephemeral0), make sure to leave the
203 # label as 'ephemeralX' otherwise there may be issues with the mounting
204 # of the ephemeral storage layer.
205 #
206 # If you define the device as 'ephemeralX.Y' then Y will be interpreted
207 # as a partition value. However, ephemeralX.0 is the _same_ as ephemeralX.
208 #
209 # <PART_VALUE>:
210 # Partition definitions are overwritten if you use the '<DEVICE>.Y' notation.
211 #
212 # The valid options are:
213 # "auto/any": tell cloud-init not to care whether there is a partition
214 # or not. Auto will use the first partition that does not contain a
215 # file system already. In the absence of a partition table, it will
216 # put it directly on the disk.
217 #
218 # "auto": If a file system that matches the specification in terms of
219 # label, type and device, then cloud-init will skip the creation of
220 # the file system.
221 #
222 # "any": If a file system that matches the file system type and device,
223 # then cloud-init will skip the creation of the file system.
224 #
225 # Devices are selected based on first-detected, starting with partitions
226 # and then the raw disk. Consider the following:
227 #     NAME      FSTYPE LABEL
228 #     xvdb
229 #     |-xvdb1  ext4
230 #     |-xvdb2
231 #     |-xvdb3  btrfs  test
232 #     \-xvdb4  ext4   test
233 #
234 # If you ask for 'auto', label of 'test', and file system of 'ext4'
235 # then cloud-init will select the 2nd partition, even though there
236 # is a partition match at the 4th partition.
237 #
238 # If you ask for 'any' and a label of 'test', then cloud-init will
239 # select the 1st partition.
240 #
241 # If you ask for 'auto' and don't define label, then cloud-init will
242 # select the 1st partition.
243 #
244 # In general, if you have a specific partition configuration in mind,
245 # you should define either the device or the partition number. 'auto'
246 # and 'any' are specifically intended for formatting ephemeral storage or
247 # for simple schemes.

```

(continues on next page)

(continued from previous page)

```

248 #
249 #     "none": Put the file system directly on the device.
250 #
251 #     <NUM>: where NUM is the actual partition number.
252 #
253 #     <OVERWRITE>: Defines whether or not to overwrite any existing
254 #     filesystem.
255 #
256 #     "true": Indiscriminately destroy any pre-existing file system. Use at
257 #     your own peril.
258 #
259 #     "false": If an existing file system exists, skip the creation.
260 #
261 #     <REPLACE_FS>: This is a special directive, used for Microsoft Azure that
262 #     instructs cloud-init to replace a file system of <FS_TYPE>. NOTE:
263 #     unless you define a label, this requires the use of the 'any' partition
264 #     directive.
265 #
266 # Behavior Caveat: The default behavior is to check if the file system exists.
267 #     If a file system matches the specification, then the operation is a no-op.

```

2.10 Events and Updates

2.10.1 Events

Cloud-init will fetch and apply cloud and user data configuration upon several event types. The two most common events for cloud-init are when an instance first boots and any subsequent boot thereafter (reboot). In addition to boot events, cloud-init users and vendors are interested in when devices are added. cloud-init currently supports the following event types:

- **BOOT_NEW_INSTANCE**: New instance first boot
- **BOOT**: Any system boot other than 'BOOT_NEW_INSTANCE'
- **BOOT_LEGACY**: Similar to 'BOOT', but applies networking config twice each boot: once during Local stage, then again in Network stage. As this behavior was previously the default behavior, this option exists to prevent regressing such behavior.
- **HOTPLUG**: Dynamic add of a system device

Future work will likely include infrastructure and support for the following events:

- **METADATA_CHANGE**: An instance's metadata has change
- **USER_REQUEST**: Directed request to update

2.10.2 Datasource Event Support

All *Datasources* by default support the `BOOT_NEW_INSTANCE` event. Each Datasource will declare a set of these events that it is capable of handling. Datasources may not support all event types. In some cases a system may be configured to allow a particular event but may be running on a platform whose datasource cannot support the event.

2.10.3 Configuring Event Updates

Update configuration may be specified via user data, which can be used to enable or disable handling of specific events. This configuration will be honored as long as the events are supported by the datasource. However, configuration will always be applied at first boot, regardless of the user data specified.

Updates

Update policy configuration defines which events are allowed to be handled. This is separate from whether a particular platform or datasource has the capability for such events.

scope: *<name of the scope for event policy>*

The `scope` value is a string which defines under which domain does the event occur. Currently the only one known scope is `network`, though more scopes may be added in the future. Scopes are defined by convention but arbitrary values can be used.

when: *<list of events to handle for a particular scope>*

Each `scope` requires a `when` element to specify which events are to allowed to be handled.

2.10.4 Hotplug

When the hotplug event is supported by the data source and configured in user data, cloud-init will respond to the addition or removal of network interfaces to the system. In addition to fetching and updating the system metadata, cloud-init will also bring up/down the newly added interface.

Warning: Due to its use of systemd sockets, hotplug functionality is currently incompatible with SELinux. This issue is being tracked [on Launchpad](#). Additionally, hotplug support is considered experimental for non-Debian based systems.

2.10.5 Examples

apply network config every boot

On every boot, apply network configuration found in the datasource.

```
# apply network config on every boot
updates:
  network:
    when: ['boot']
```

2.11 Merging User-Data Sections

2.11.1 Overview

This was implemented because it has been a common feature request that there be a way to specify how cloud-config YAML “dictionaries” provided as user-data are merged together when there are multiple YAML files to merge together (say when performing an `#include`).

Since previously the merging algorithm was very simple and would only overwrite and not append lists, or strings, and so on it was decided to create a new and improved way to merge dictionaries (and their contained objects) together in a way that is customizable, thus allowing for users who provide cloud-config user-data to determine exactly how their objects will be merged.

For example.

```
#cloud-config (1)
runcmd:
  - bash1
  - bash2

#cloud-config (2)
runcmd:
  - bash3
  - bash4
```

The previous way of merging the two objects above would result in a final cloud-config object that contains the following.

```
#cloud-config (merged)
runcmd:
  - bash3
  - bash4
```

Typically this is not what users want; instead they would likely prefer:

```
#cloud-config (merged)
runcmd:
  - bash1
  - bash2
  - bash3
  - bash4
```

This way makes it easier to combine the various cloud-config objects you have into a more useful list, thus reducing duplication necessary to accomplish the same result with the previous method.

2.11.2 Built-in Mergers

Cloud-init provides merging for the following built-in types:

- Dict
- List
- String

The Dict merger has the following options which control what is done with values contained within the config.

- `allow_delete`: Existing values not present in the new value can be deleted, defaults to False
- `no_replace`: Do not replace an existing value if one is already present, enabled by default.
- `replace`: Overwrite existing values with new ones.

The List merger has the following options which control what is done with the values contained within the config.

- `append`: Add new value to the end of the list, defaults to False.
- `prepend`: Add new values to the start of the list, defaults to False.
- `no_replace`: Do not replace an existing value if one is already present, enabled by default.
- `replace`: Overwrite existing values with new ones.

The Str merger has the following options which control what is done with the values contained within the config.

- `append`: Add new value to the end of the string, defaults to False.

Common options for all merge types which control how recursive merging is done on other types.

- `recurse_dict`: If True merge the new values of the dictionary, defaults to True.
- `recurse_list`: If True merge the new values of the list, defaults to False.
- `recurse_array`: Alias for `recurse_list`.
- `recurse_str`: If True merge the new values of the string, defaults to False.

2.11.3 Customizability

Because the above merging algorithm may not always be desired (just as the previous merging algorithm was not always the preferred one), the concept of customized merging was introduced through ‘merge classes’.

A merge class is a class definition which provides functions that can be used to merge a given type with another given type.

An example of one of these merging classes is the following:

```
class Merger:
    def __init__(self, merger, opts):
        self._merger = merger
        self._overwrite = 'overwrite' in opts

    # This merging algorithm will attempt to merge with
    # another dictionary, on encountering any other type of object
    # it will not merge with said object, but will instead return
    # the original value
    #
    # On encountering a dictionary, it will create a new dictionary
```

(continues on next page)

(continued from previous page)

```
# composed of the original and the one to merge with, if 'overwrite'
# is enabled then keys that exist in the original will be overwritten
# by keys in the one to merge with (and associated values). Otherwise
# if not in overwrite mode the 2 conflicting keys themselves will
# be merged.
def _on_dict(self, value, merge_with):
    if not isinstance(merge_with, (dict)):
        return value
    merged = dict(value)
    for (k, v) in merge_with.items():
        if k in merged:
            if not self._overwrite:
                merged[k] = self._merger.merge(merged[k], v)
            else:
                merged[k] = v
        else:
            merged[k] = v
    return merged
```

As you can see there is a ‘_on_dict’ method here that will be given a source value and a value to merge with. The result will be the merged object. This code itself is called by another merging class which ‘directs’ the merging to happen by analyzing the types of the objects to merge and attempting to find a known object that will merge that type. I will avoid pasting that here, but it can be found in the *mergers/__init__.py* file (see *LookupMerger* and *UnknownMerger*).

So following the typical cloud-init way of allowing source code to be downloaded and used dynamically, it is possible for users to inject their own merging files to handle specific types of merging as they choose (the basic ones included will handle lists, dicts, and strings). Note how each merge can have options associated with it which affect how the merging is performed, for example a dictionary merger can be told to overwrite instead of attempt to merge, or a string merger can be told to append strings instead of discarding other strings to merge with.

2.11.4 How to activate

There are a few ways to activate the merging algorithms, and to customize them for your own usage.

1. The first way involves the usage of MIME messages in cloud-init to specify multipart documents (this is one way in which multiple cloud-config is joined together into a single cloud-config). Two new headers are looked for, both of which can define the way merging is done (the first header to exist wins). These new headers (in lookup order) are ‘Merge-Type’ and ‘X-Merge-Type’. The value should be a string which will satisfy the new merging format definition (see below for this format).
2. The second way is actually specifying the merge-type in the body of the cloud-config dictionary. There are 2 ways to specify this, either as a string or as a dictionary (see format below). The keys that are looked up for this definition are the following (in order), ‘merge_how’, ‘merge_type’.

String format

The string format that is expected is the following.

```
classname1(option1,option2)+classname2(option3,option4)...
```

The class name there will be connected to class names used when looking for the class that can be used to merge and options provided will be given to the class on construction of that class.

For example, the default string that is used when none is provided is the following:

```
list()+dict()+str()
```

Dictionary format

A dictionary can be used when it specifies the same information as the string format (i.e. the second option above), for example:

```
{'merge_how': [{'name': 'list', 'settings': ['append']},
               {'name': 'dict', 'settings': ['no_replace', 'recurse_list']},
               {'name': 'str', 'settings': ['append']}]}
```

This would be the equivalent format for default string format but in dictionary form instead of string form.

2.11.5 Specifying multiple types and its effect

Now you may be asking yourself, if I specify a merge-type header or dictionary for every cloud-config that I provide, what exactly happens?

The answer is that when merging, a stack of ‘merging classes’ is kept, the first one on that stack is the default merging classes, this set of mergers will be used when the first cloud-config is merged with the initial empty cloud-config dictionary. If the cloud-config that was just merged provided a set of merging classes (via the above formats) then those merging classes will be pushed onto the stack. Now if there is a second cloud-config to be merged then the merging classes from the cloud-config before the first will be used (not the default) and so on. This way a cloud-config can decide how it will merge with a cloud-config dictionary coming after it.

2.11.6 Other uses

In addition to being used for merging user-data sections, the default merging algorithm for merging ‘conf.d’ YAML files (which form an initial YAML config for cloud-init) was also changed to use this mechanism so its full benefits (and customization) can also be used there as well. Other places that used the previous merging are also, similarly, now extensible (metadata merging, for example).

Note, however, that merge algorithms are not used *across* types of configuration. As was the case before merging was implemented, user-data will overwrite conf.d configuration without merging.

2.11.7 Example cloud-config

A common request is to include multiple `runcmd` directives in different files and merge all of the commands together. To achieve this, we must modify the default merging to allow for dictionaries to join list values.

The first config

```
#cloud-config
merge_how:
- name: list
  settings: [append]
- name: dict
  settings: [no_replace, recurse_list]

runcmd:
- bash1
- bash2
```

The second config

```
#cloud-config
merge_how:
- name: list
  settings: [append]
- name: dict
  settings: [no_replace, recurse_list]

runcmd:
- bash3
- bash4
```

2.12 Instance Metadata

2.12.1 Kernel Command Line

In order to allow an ephemeral, or otherwise pristine image to receive some configuration, cloud-init will read a url directed by the kernel command line and proceed as if its data had previously existed.

This allows for configuring a meta-data service, or some other data.

Note: That usage of the kernel command line is somewhat of a last resort, as it requires knowing in advance the correct command line or modifying the boot loader to append data.

For example, when `cloud-init init --local` runs, it will check to see if `cloud-config-url` appears in key/value fashion in the kernel command line as in:

```
root=/dev/sda ro cloud-config-url=http://foo.bar.zee/abcde
```

Cloud-init will then read the contents of the given url. If the content starts with `#cloud-config`, it will store that data to the local filesystem in a static filename `/etc/cloud/cloud.cfg.d/91_kernel_cmdline_url.cfg`, and consider it as part of the config from that point forward.

If that file exists already, it will not be overwritten, and the `cloud-config-url` parameter is completely ignored.

Then, when the DataSource runs, it will find that config already available.

So, in order to be able to configure the MAAS DataSource by controlling the kernel command line from outside the image, you can append:

- `cloud-config-url=http://your.url.here/abcdefg`

Then, have the following content at that url:

```
#cloud-config
datasource:
  MAAS:
    metadata_url: http://mass-host.localdomain/source
    consumer_key: Xh234sdlkfj
    token_key: kjfhgb3n
    token_secret: 24uysdfx1w4
```

Warning: `url` kernel command line key is deprecated. Please use `cloud-config-url` parameter instead”

Note: Because `cloud-config-url=` is so very generic, in order to avoid false positives, cloud-init requires the content to start with `#cloud-config` in order for it to be considered.

Note: The `cloud-config-url=` is un-authed http GET, and contains credentials. It could be set up to be randomly generated and also check source address in order to be more secure.

2.12.2 What is instance-data?

Each cloud provider presents unique configuration metadata to a launched cloud instance. Cloud-init crawls this meta-data and then caches and exposes this information as a standardized and versioned JSON object known as instance-data. This instance-data may then be queried or later used by cloud-init in templated configuration and scripts.

An example of a small subset of instance-data on a launched EC2 instance:

```
{
  "v1": {
    "cloud_name": "aws",
    "distro": "ubuntu",
    "distro_release": "jammy",
    "distro_version": "22.04",
    "instance_id": "i-06b5687b4d7b8595d",
    "machine": "x86_64",
    "platform": "ec2",
    "python_version": "3.10.4",
    "region": "us-east-2",
    "variant": "ubuntu"
  }
}
```

2.12.3 Discovery

One way to easily explore what instance-data variables are available on your machine is to use the *cloud-init query* tool. Warnings or exceptions will be raised on invalid instance-data keys, paths or invalid syntax.

The **query** command also publishes **userdata** and **vendordata** keys to the root user which will contain the decoded user and vendor data provided to this instance. Non-root users referencing **userdata** or **vendordata** keys will see only redacted values.

Note: To save time designing a user-data template for a specific cloud's instance-data.json, use the 'render' cloud-init command on an instance booted on your favorite cloud. See *devel* for more information.

2.12.4 Using instance-data

Instance-data can be used in:

- *User-data scripts*
- *Cloud-config data*
- *Base configuration*
- Command line interface via **cloud-init query** or **cloud-init devel render**

The aforementioned configuration sources support jinja template rendering. When the first line of the provided configuration begins with **## template: jinja**, cloud-init will use jinja to render that file. Any instance-data variables are surfaced as jinja template variables.

Note: Trying to reference jinja variables that don't exist in instance-data will result in warnings in `/var/log/cloud-init.log` and the following string in your rendered user-data: `CI_MISSING_JINJA_VAR/<your_varname>`.

Sensitive data such as user passwords may be contained in instance-data. Cloud-init separates this sensitive data such that it is only readable by root. In the case that a non-root user attempts to read sensitive instance-data, they will receive redacted data or same warnings and text that occur if a variable does not exist.

Example Usage

Cloud config with instance-data

```
## template: jinja
#cloud-config
runcmd:
  - echo 'EC2 public hostname allocated to instance: {{
    ds.meta_data.public_hostname }}' > /tmp/instance_metadata
  - echo 'EC2 availability zone: {{ v1.availability_zone }}' >>
    /tmp/instance_metadata
  - curl -X POST -d '{"hostname": "{{ds.meta_data.public_hostname }}",
    "availability-zone": "{{ v1.availability_zone }}"}'
    https://example.com
```

User-data script with instance-data

```
## template: jinja
#!/bin/bash
{% if v1.region == 'us-east-2' -%}
echo 'Installing custom proxies for {{ v1.region }}'
sudo apt-get install my-xtra-fast-stack
{%- endif %}
...
```

CLI discovery of instance-data

```
# List all instance-data keys and values as root user
% sudo cloud-init query --all
{...}

# List all top-level instance-data keys available
% cloud-init query --list-keys

# Introspect nested keys on an object
% cloud-init query -f "{{ds.keys()}}"
dict_keys(['meta_data', '_doc'])

# Failure to reference valid dot-delimited key path on a known top-level key
% cloud-init query v1.not_here
ERROR: instance-data 'v1' has no 'not_here'

# Test expected value using valid instance-data key path
% cloud-init query -f "My AMI: {{ds.meta_data.ami_id}}"
My AMI: ami-0fecc35d3c8ba8d60

# The --format command renders jinja templates, this can also be used
# to develop and test jinja template constructs
% cat > test-templating.yaml <<EOF
{% for val in ds.meta_data.keys() %}
- {{ val }}
{% endfor %}
EOF
% cloud-init query --format="$$( cat test-templating.yaml )"
- instance_id
- dsmode
- local_hostname
```

2.12.5 Reference

Storage Locations

- `/run/cloud-init/instance-data.json`: world-readable json containing standardized keys, sensitive keys redacted
- `/run/cloud-init/instance-data-sensitive.json`: root-readable unredacted json blob

Format of instance-data.json

Top-level keys:

- **base64_encoded_keys**: A list of forward-slash delimited key paths into the instance-data.json object whose value is base64encoded for json compatibility. Values at these paths should be decoded to get the original value.
- **sensitive_keys**: A list of forward-slash delimited key paths into the instance-data.json object whose value is considered by the datasource as 'security sensitive'. Only the keys listed here will be redacted from instance-data.json for non-root users.
- **merged_cfg**: Merged cloud-init *Base Configuration* from `/etc/cloud/cloud.cfg` and `/etc/cloud/cloud-cfg.d`. Values under this key could contain sensitive information such as passwords, so it is included in the **sensitive-keys** list which is only readable by root.
- **ds**: Datasource-specific metadata crawled for the specific cloud platform. It should closely represent the structure of the cloud metadata crawled. The structure of content and details provided are entirely cloud-dependent. Mileage will vary depending on what the cloud exposes. The content exposed under the 'ds' key is currently **experimental** and expected to change slightly in the upcoming cloud-init release.
- **sys_info**: Information about the underlying os, python, architecture and kernel. This represents the data collected by `cloudinit.util.system_info`.
- **v1**: Standardized cloud-init metadata keys, these keys are guaranteed to exist on all cloud platforms. They will also retain their current behavior and format and will be carried forward even if cloud-init introduces a new version of standardized keys with **v2**.

To cut down on keystrokes on the command line, cloud-init also provides top-level key aliases for any standardized **v#** keys present. The preceding **v1** is not required of **v1.var_name**. These aliases will represent the value of the highest versioned standard key. For example, `cloud_name` value will be `v2.cloud_name` if both **v1** and **v2** keys are present in instance-data.json.

cloud-init also provides jinja-safe key aliases for any instance-data keys which contain jinja operator characters such as `+`, `-`, `.`, `/`, etc. Any jinja operator will be replaced with underscores in the jinja-safe key alias. This allows for cloud-init templates to use aliased variable references which allow for jinja's dot-notation reference such as `{{ ds.v1_0.my_safe_key }}` instead of `{{ ds["v1.0"]["my/safe-key"] }}`.

The standardized keys present:

v1._beta_keys

List of standardized keys still in ‘beta’. The format, intent or presence of these keys can change. Do not consider them production-ready.

Example output:

- [subplatform]

v1.cloud_name

Where possible this will indicate the ‘name’ of the cloud the system is running on. This is different than the ‘platform’ item. For example, the cloud name of Amazon Web Services is ‘aws’, while the platform is ‘ec2’.

If determining a specific name is not possible or provided in meta-data, then this file may contain the same content as ‘platform’.

Example output:

- aws
- openstack
- azure
- configdrive
- nocloud
- ovf

v1.distro, v1.distro_version, v1.distro_release

This shall be the distro name, version and release as determined by *cloudinit.util.get_linux_distro*.

Example output:

- alpine, 3.12.0, ‘
- centos, 7.5, core
- debian, 9, stretch
- freebsd, 12.0-release-p10,
- opensuse, 42.3, x86_64
- opensuse-tumbleweed, 20180920, x86_64
- redhat, 7.5, ‘maipo’
- sles, 12.3, x86_64
- ubuntu, 20.04, focal

v1.instance_id

Unique instance_id allocated by the cloud.

Examples output:

- i-<hash>

v1.kernel_release

This shall be the running kernel *uname -r*

Example output:

- 5.3.0-1010-aws

v1.local_hostname

The internal or local hostname of the system.

Examples output:

- ip-10-41-41-70
- <user-provided-hostname>

v1.machine

This shall be the running cpu machine architecture *uname -m*

Example output:

- x86_64
- i686
- ppc64le
- s390x

v1.platform

An attempt to identify the cloud platform instance that the system is running on.

Examples output:

- ec2
- openstack
- lxd
- gce
- nocloud
- ovf

v1.subplatform

Additional platform details describing the specific source or type of metadata used. The format of subplatform will be: `<subplatform_type> (<url_file_or_dev_path>)`

Examples output:

- metadata (<http://168.254.169.254>)
- seed-dir (/path/to/seed-dir/)
- config-disk (/dev/cd0)
- configdrive (/dev/sr0)

v1.public_ssh_keys

A list of SSH keys provided to the instance by the datasource metadata.

Examples output:

- ['ssh-rsa AA...', ...]

v1.python_version

The version of python that is running cloud-init as determined by *cloudinit.util.system_info*

Example output:

- 3.7.6

v1.region

The physical region/data center in which the instance is deployed.

Examples output:

- us-east-2

v1.availability_zone

The physical availability zone in which the instance is deployed.

Examples output:

- us-east-2b
- nova
- null

Example Output

Below is an example of `/run/cloud-init/instance-data-sensitive.json` on an EC2 instance:

```
{
  "_beta_keys": [
    "subplatform"
  ],
  "availability_zone": "us-east-1b",
  "base64_encoded_keys": [],
  "merged_cfg": {
    "_doc": "Merged cloud-init base config from /etc/cloud/cloud.cfg and /etc/cloud/cloud.
↪cfg.d/",
    "_log": [
      "[loggers]\nkeys=root,cloudinit\n\n[handlers]\nkeys=consoleHandler,cloudLogHandler\n\n
↪[formatters]\nkeys=simpleFormatter,arg0Formatter\n\n[logger_root]\nlevel=DEBUG\n
↪nhandlers=consoleHandler,cloudLogHandler\n\n[logger_cloudinit]\nlevel=DEBUG\n
↪nqualname=cloudinit\nnhandlers=\npropagate=1\n\n[handler_consoleHandler]\n
↪nclass=StreamHandler\nlevel=WARNING\nformatter=arg0Formatter\nargs=(sys.stderr,)\n\n
↪n[formatter_arg0Formatter]\nformat=%(asctime)s - %(filename)s[%(levelname)s]:
↪%(message)s\n\n[formatter_simpleFormatter]\nformat=[CLOUDINIT] %(filename)s[
↪%(levelname)s]: %(message)s\n",
      "[handler_cloudLogHandler]\nnclass=FileHandler\nlevel=DEBUG\nformatter=arg0Formatter\n
↪nargs=(' /var/log/cloud-init.log',)\n",
      "[handler_cloudLogHandler]\nnclass=handlers.SysLogHandler\nlevel=DEBUG\n
↪nformatter=simpleFormatter\nargs=(\" /dev/log\", handlers.SysLogHandler.LOG_USER)\n"
    ],
    "cloud_config_modules": [
      "snap",
      "ssh-import-id",
      "locale",
      "set-passwords",
      "grub-dpkg",
      "apt-pipelining",
      "apt-configure",
      "ubuntu-advantage",
      "ntp",
      "timezone",
      "disable-ec2-metadata",
      "runcmd",
      "byobu"
    ],
    "cloud_final_modules": [
      "package-update-upgrade-install",
      "fan",
      "landscape",
      "lxd",
      "ubuntu-drivers",
      "puppet",
      "chef",
      "mcollective",
      "salt-minion",
      "rightscale_userdata",

```

(continues on next page)

(continued from previous page)

```
"scripts-vendor",
"scripts-per-once",
"scripts-per-boot",
"scripts-per-instance",
"scripts-user",
"ssh-authkey-fingerprints",
"keys-to-console",
"phone-home",
"final-message",
"power-state-change"
],
"cloud_init_modules": [
    "migrator",
    "seed_random",
    "bootcmd",
    "write-files",
    "growpart",
    "resizefs",
    "disk_setup",
    "mounts",
    "set_hostname",
    "update_hostname",
    "update_etc_hosts",
    "ca-certs",
    "rsyslog",
    "users-groups",
    "ssh"
],
"datasource_list": [
    "Ec2",
    "None"
],
"def_log_file": "/var/log/cloud-init.log",
"disable_root": true,
"log_cfgs": [
    [
        "loggers]\nkeys=root,cloudinit\n\n[handlers]\nkeys=consoleHandler,cloudLogHandler\n\n[n[formatters]\nkeys=simpleFormatter,arg0Formatter\n\n\n[logger_root]\nlevel=DEBUG\n\n\n[nhandlers=consoleHandler,cloudLogHandler\n\n\n[logger_cloudinit]\nlevel=DEBUG\n\n\n[nqualname=cloudinit\n\n\n[nhandlers=\n\n\npropagate=1\n\n\n\n[handler_consoleHandler]\n\n\n[class=StreamHandler\n\n\nlevel=WARNING\n\n\nformatter=arg0Formatter\n\n\nargs=(sys.stderr,)\n\n\n\n[n[formatter_arg0Formatter]\n\n\nformat=%(asctime)s - %(filename)s[%](levelname)s]:\n\n\n%(message)s\n\n\n\n[n[formatter_simpleFormatter]\n\n\nformat=[CLOUDINIT] %(filename)s[\n\n\n%(levelname)s]: %(message)s\n",
        "[handler_cloudLogHandler]\n\n\n[class=FileHandler\n\n\nlevel=DEBUG\n\n\nformatter=arg0Formatter\n\n\n\nargs=(' /var/log/cloud-init.log', )\n\n"
    ]
],
"output": {
    "all": "| tee -a /var/log/cloud-init-output.log"
},
"preserve_hostname": false,
```

(continues on next page)

(continued from previous page)

```

"syslog_fix_perms": [
  "syslog:adm",
  "root:adm",
  "root:wheel",
  "root:root"
],
"users": [
  "default"
],
"vendor_data": {
  "enabled": true,
  "prefix": []
}
},
"cloud_name": "aws",
"distro": "ubuntu",
"distro_release": "focal",
"distro_version": "20.04",
"ds": {
  "_doc": "EXPERIMENTAL: The structure and format of content scoped under the 'ds' key
↪ may change in subsequent releases of cloud-init.",
  "_metadata_api_version": "2016-09-02",
  "dynamic": {
    "instance_identity": {
      "document": {
        "accountId": "329910648901",
        "architecture": "x86_64",
        "availabilityZone": "us-east-1b",
        "billingProducts": null,
        "devpayProductCodes": null,
        "imageId": "ami-02e8aa396f8be3b6d",
        "instanceId": "i-0929128ff2f73a2f1",
        "instanceType": "t2.micro",
        "kernelId": null,
        "marketplaceProductCodes": null,
        "pendingTime": "2020-02-27T20:46:18Z",
        "privateIp": "172.31.81.43",
        "ramdiskId": null,
        "region": "us-east-1",
        "version": "2017-09-30"
      },
    },
    "pkcs7": [
      "MIAGCSqGSIB3DQ...",
      "REDACTED",
      "AhQUgqQiPWqPTVnT96tZE6L1XjjLHQAAAAAAAAA=="
    ],
    "rsa2048": [
      "MIAGCSqGSIB...",
      "REDACTED",
      "cLYQvuE45xXm7Yreg3QtQbrP//ow11eZHj6s350AAAAAAAAA="
    ],
    "signature": [

```

(continues on next page)

(continued from previous page)

```

    "dA+QV+LLCWCNRddnrKleYmh2GvYo+t8urDkdgmDSsPi",
    "REDACTED",
    "kDT4ygyJLFkd3b4qjAs="
  ]
},
"meta_data": {
  "ami_id": "ami-02e8aa396f8be3b6d",
  "ami_launch_index": "0",
  "ami_manifest_path": "(unknown)",
  "block_device_mapping": {
    "ami": "/dev/sda1",
    "root": "/dev/sda1"
  },
  "hostname": "ip-172-31-81-43.ec2.internal",
  "instance_action": "none",
  "instance_id": "i-0929128ff2f73a2f1",
  "instance_type": "t2.micro",
  "local_hostname": "ip-172-31-81-43.ec2.internal",
  "local_ipv4": "172.31.81.43",
  "mac": "12:7e:c9:93:29:af",
  "metrics": {
    "vhostmd": "<?xml version=\"1.0\" encoding=\"UTF-8\"?>"
  },
  "network": {
    "interfaces": {
      "macs": {
        "12:7e:c9:93:29:af": {
          "device_number": "0",
          "interface_id": "eni-0c07a0474339b801d",
          "ipv4_associations": {
            "3.89.187.177": "172.31.81.43"
          },
          "local_hostname": "ip-172-31-81-43.ec2.internal",
          "local_ipv4s": "172.31.81.43",
          "mac": "12:7e:c9:93:29:af",
          "owner_id": "329910648901",
          "public_hostname": "ec2-3-89-187-177.compute-1.amazonaws.com",
          "public_ipv4s": "3.89.187.177",
          "security_group_ids": "sg-0100038b68aa79986",
          "security_groups": "launch-wizard-3",
          "subnet_id": "subnet-04e2d12a",
          "subnet_ipv4_cidr_block": "172.31.80.0/20",
          "vpc_id": "vpc-210b4b5b",
          "vpc_ipv4_cidr_block": "172.31.0.0/16",
          "vpc_ipv4_cidr_blocks": "172.31.0.0/16"
        }
      }
    }
  },
  "placement": {
    "availability_zone": "us-east-1b"
  }
}

```

(continues on next page)

(continued from previous page)

```

    },
    "profile": "default-hvm",
    "public_hostname": "ec2-3-89-187-177.compute-1.amazonaws.com",
    "public_ipv4": "3.89.187.177",
    "reservation_id": "r-0c481643d15766a02",
    "security_groups": "launch-wizard-3",
    "services": {
        "domain": "amazonaws.com",
        "partition": "aws"
    }
},
{
    "instance_id": "i-0929128ff2f73a2f1",
    "kernel_release": "5.3.0-1010-aws",
    "local_hostname": "ip-172-31-81-43",
    "machine": "x86_64",
    "platform": "ec2",
    "public_ssh_keys": [],
    "python_version": "3.7.6",
    "region": "us-east-1",
    "sensitive_keys": [],
    "subplatform": "metadata (http://169.254.169.254)",
    "sys_info": {
        "dist": [
            "ubuntu",
            "20.04",
            "focal"
        ],
        "platform": "Linux-5.3.0-1010-aws-x86_64-with-Ubuntu-20.04-focal",
        "python": "3.7.6",
        "release": "5.3.0-1010-aws",
        "system": "Linux",
        "uname": [
            "Linux",
            "ip-172-31-81-43",
            "5.3.0-1010-aws",
            "#11-Ubuntu SMP Thu Jan 16 07:59:32 UTC 2020",
            "x86_64",
            "x86_64"
        ],
        "variant": "ubuntu"
    },
    "system_platform": "Linux-5.3.0-1010-aws-x86_64-with-Ubuntu-20.04-focal",
    "userdata": "#cloud-config\nssh_import_id: [<my-launchpad-id>]\n...",
    "v1": {
        "_beta_keys": [
            "subplatform"
        ],
        "availability_zone": "us-east-1b",
        "cloud_name": "aws",
        "distro": "ubuntu",
        "distro_release": "focal",

```

(continues on next page)

(continued from previous page)

```

"distro_version": "20.04",
"instance_id": "i-0929128ff2f73a2f1",
"kernel": "5.3.0-1010-aws",
"local_hostname": "ip-172-31-81-43",
"machine": "x86_64",
"platform": "ec2",
"public_ssh_keys": [],
"python": "3.7.6",
"region": "us-east-1",
"subplatform": "metadata (http://169.254.169.254)",
"system_platform": "Linux-5.3.0-1010-aws-x86_64-with-Ubuntu-20.04-focal",
"variant": "ubuntu"
},
"variant": "ubuntu",
"vendordata": ""
}

```

2.13 Datasources

Datasources are sources of configuration data for cloud-init that typically come from the user (i.e. userdata) or come from the cloud that created the configuration drive (i.e. metadata). Typical userdata would include files, YAML, and shell scripts while typical metadata would include server name, instance id, display name and other cloud specific details.

Since there are multiple ways to provide this data (each cloud solution seems to prefer its own way) internally a data-source abstract class was created to allow for a single way to access the different cloud systems methods to provide this data through the typical usage of subclasses.

Any metadata processed by cloud-init's datasources is persisted as `/run/cloud-init/instance-data.json`. Cloud-init provides tooling to quickly introspect some of that data. See [Instance Metadata](#) for more information.

2.13.1 Known Sources

The following is a list of documents for each supported datasource:

Alibaba Cloud (AliYun)

The AliYun datasource reads data from Alibaba Cloud ECS. Support is present in cloud-init since 0.7.9.

Metadata Service

The Alibaba Cloud metadata service is available at the well known url `http://100.100.100.200/`. For more information see Alibaba Cloud ECS on [metadata](#).

Configuration

The following configuration can be set for the datasource in system configuration (in `/etc/cloud/cloud.cfg` or `/etc/cloud/cloud.cfg.d/`).

An example configuration with the default values is provided below:

```
datasource:
  AliYun:
    metadata_urls: ["http://100.100.100.200"]
    timeout: 50
    max_wait: 120
```

Versions

Like the EC2 metadata service, Alibaba Cloud's metadata service provides versioned data under specific paths. As of April 2018, there are only `2016-01-01` and `latest` versions.

It is expected that the dated version will maintain a stable interface but `latest` may change content at a future date.

Cloud-init uses the `2016-01-01` version.

You can list the versions available to your instance with:

```
$ curl http://100.100.100.200/
2016-01-01
latest
```

Metadata

Instance metadata can be queried at `http://100.100.100.200/2016-01-01/meta-data`

```
$ curl http://100.100.100.200/2016-01-01/meta-data
dns-conf/
eipv4
hostname
image-id
instance-id
instance/
mac
network-type
network/
ntp-conf/
owner-account-id
private-ipv4
public-keys/
region-id
serial-number
source-address
sub-private-ipv4-list
vpc-cidr-block
vpc-id
```

Userdata

If provided, user-data will appear at `http://100.100.100.200/2016-01-01/user-data`. If no user-data is provided, this will return a 404.

```
$ curl http://100.100.100.200/2016-01-01/user-data
#!/bin/sh
echo "Hello World."
```

Alt Cloud

The datasource altcloud will be used to pick up user data on [RHEVm](#) and [vSphere](#).

RHEVm

For [RHEVm](#) v3.0 the userdata is injected into the VM using floppy injection via the [RHEVm](#) dashboard “Custom Properties”.

The format of the Custom Properties entry must be:

```
floppyinject=user-data.txt:<base64 encoded data>
```

For example to pass a simple bash script:

```
% cat simple_script.bash
#!/bin/bash
echo "Hello Joe!" >> /tmp/JJV_Joe_out.txt

% base64 < simple_script.bash
IyEvYmluL2Jhc2gKZWNoYAiSGVsbG8gSm9lISIgPj4gL3RtcC9KS1ZfSm9lX291dC50eHQK
```

To pass this example script to cloud-init running in a [RHEVm](#) v3.0 VM set the “Custom Properties” when creating the [RHEMv](#) v3.0 VM to:

```
floppyinject=user-data.
↪txt:IyEvYmluL2Jhc2gKZWNoYAiSGVsbG8gSm9lISIgPj4gL3RtcC9KS1ZfSm9lX291dC50eHQK
```

NOTE: The prefix with file name must be: `floppyinject=user-data.txt:`

It is also possible to launch a [RHEVm](#) v3.0 VM and pass optional user data to it using the Delta Cloud.

For more information on Delta Cloud see: <http://deltacloud.apache.org>

vSphere

For VMWare’s [vSphere](#) the userdata is injected into the VM as an ISO via the cdrom. This can be done using the [vSphere](#) dashboard by connecting an ISO image to the CD/DVD drive.

To pass this example script to cloud-init running in a [vSphere](#) VM set the CD/DVD drive when creating the [vSphere](#) VM to point to an ISO on the data store.

Note: The ISO must contain the user data.

For example, to pass the same `simple_script.bash` to [vSphere](#):

Create the ISO

```
% mkdir my-iso
```

NOTE: The file name on the ISO must be: `user-data.txt`

```
% cp simple_script.bash my-iso/user-data.txt
% genisoimage -o user-data.iso -r my-iso
```

Verify the ISO

```
% sudo mkdir /media/vsphere_iso
% sudo mount -o loop user-data.iso /media/vsphere_iso
% cat /media/vsphere_iso/user-data.txt
% sudo umount /media/vsphere_iso
```

Then, launch the **vSphere** VM the ISO `user-data.iso` attached as a CDROM.

It is also possible to launch a **vSphere** VM and pass optional user data to it using the Delta Cloud.

For more information on Delta Cloud see: <http://deltacloud.apache.org>

Amazon EC2

The EC2 datasource is the oldest and most widely used datasource that cloud-init supports. This datasource interacts with a *magic* ip that is provided to the instance by the cloud provider. Typically this ip is `169.254.169.254` of which at this ip a http server is provided to the instance so that the instance can make calls to get instance userdata and instance metadata.

Metadata is accessible via the following URL:

```
GET http://169.254.169.254/2009-04-04/meta-data/
ami-id
ami-launch-index
ami-manifest-path
block-device-mapping/
hostname
instance-id
instance-type
local-hostname
local-ipv4
placement/
public-hostname
public-ipv4
public-keys/
reservation-id
security-groups
```

Userdata is accessible via the following URL:

```
GET http://169.254.169.254/2009-04-04/user-data
1234,fred,reboot,true | 4512,jimbo, | 173,,,
```

Note that there are multiple EC2 Metadata versions of this data provided to instances. cloud-init will attempt to use the most recent API version it supports in order to get latest API features and instance-data. If a given API version is not exposed to the instance, those API features will be unavailable to the instance.

EC2 version	supported instance-data/feature
2021-03-23	Required for Instance tag support. This feature must be enabled individually on each instance. See the EC2 tags user guide .
2016-09-02	Required for secondary IP address support.
2009-04-04	Minimum supports EC2 API version for meta-data and user-data.

To see which versions are supported from your cloud provider use the following URL:

```
GET http://169.254.169.254/
1.0
2007-01-19
2007-03-01
2007-08-29
2007-10-10
2007-12-15
2008-02-01
2008-09-01
2009-04-04
...
latest
```

Configuration

The following configuration can be set for the datasource in system configuration (in `/etc/cloud/cloud.cfg` or `/etc/cloud/cloud.cfg.d/`).

The settings that may be configured are:

- **metadata_urls**: This list of urls will be searched for an EC2 metadata service. The first entry that successfully returns a 200 response for `<url>/<version>/meta-data/instance-id` will be selected. (default: `['http://169.254.169.254', 'http://[::fd00:ec2::254]', 'http://instance-data:8773']`).
- **max_wait**: the maximum amount of clock time in seconds that should be spent searching `metadata_urls`. A value less than zero will result in only one request being made, to the first in the list. (default: 120)
- **timeout**: the timeout value provided to `urlopen` for each individual http request. This is used both when selecting a `metadata_url` and when crawling the metadata service. (default: 50)
- **apply_full_imds_network_config**: Boolean (default: True) to allow cloud-init to configure any secondary NICs and secondary IPs described by the metadata service. All network interfaces are configured with DHCP (v4) to obtain an primary IPv4 address and route. Interfaces which have a non-empty `ipv6s` list will also enable DHCPv6 to obtain a primary IPv6 address and route. The DHCP response (v4 and v6) return an IP that matches the first element of `local-ipv4s` and `ipv6s` lists respectively. All additional values (secondary addresses) in the static ip lists will be added to interface.

An example configuration with the default values is provided below:

```
datasource:
  Ec2:
    metadata_urls: ["http://169.254.169.254:80", "http://instance-data:8773"]
    max_wait: 120
    timeout: 50
    apply_full_imds_network_config: true
```

Notes

- There are 2 types of EC2 instances network-wise: VPC ones (Virtual Private Cloud) and Classic ones (also known as non-VPC). One major difference between them is that Classic instances have their MAC address changed on stop/restart operations, so cloud-init will recreate the network config file for EC2 Classic instances every boot. On VPC instances this file is generated only in the first boot of the instance. The check for the instance type is performed by `is_classic_instance()` method.
- For EC2 instances with multiple network interfaces (NICs) attached, dhcp4 will be enabled to obtain the primary private IPv4 address of those NICs. Wherever dhcp4 or dhcp6 is enabled for a NIC, a dhcp route-metric will be added with the value of `<device-number + 1> * 100` to ensure dhcp routes on the primary NIC are preferred to any secondary NICs. For example: the primary NIC will have a DHCP route-metric of 100, the next NIC will be 200.

Azure

This datasource finds metadata and user-data from the Azure cloud platform.

The Azure cloud platform provides initial data to an instance via an attached CD formatted in UDF. That CD contains a 'ovf-env.xml' file that provides some information. Additional information is obtained via interaction with the "endpoint".

IMDS

Azure provides the [instance metadata service \(IMDS\)](#) which is a REST service on 169.254.169.254 providing additional configuration information to the instance. Cloud-init uses the IMDS for:

- network configuration for the instance which is applied per boot
- a preprovisioning gate which blocks instance configuration until Azure fabric is ready to provision
- retrieving SSH public keys. Cloud-init will first try to utilize SSH keys returned from IMDS, and if they are not provided from IMDS then it will fallback to using the OVF file provided from the CD-ROM. There is a large performance benefit to using IMDS for SSH key retrieval, but in order to support environments where IMDS is not available then we must continue to all for keys from OVF

Configuration

The following configuration can be set for the datasource in system configuration (in `/etc/cloud/cloud.cfg` or `/etc/cloud/cloud.cfg.d/`).

The settings that may be configured are:

- **apply_network_config**: Boolean set to True to use network configuration described by Azure's IMDS endpoint instead of fallback network config of dhcp on eth0. Default is True. For Ubuntu 16.04 or earlier, default is False.
- **data_dir**: Path used to read metadata files and write crawled data.
- **disk_aliases**: A dictionary defining which device paths should be interpreted as ephemeral images. See `cc_disk_setup` module for more info.

Configuration for the datasource can also be read from a `dscfg` entry in the `LinuxProvisioningConfigurationSet`. Content in `dscfg` node is expected to be base64 encoded yaml content, and it will be merged into the 'datasource: Azure' entry.

An example configuration with the default values is provided below:

```
datasource:
  Azure:
    apply_network_config: true
    data_dir: /var/lib/waagent
    disk_aliases:
      ephemeral0: /dev/disk/cloud/azure_resource
```

Userdata

Userdata is provided to cloud-init inside the `ovf-env.xml` file. Cloud-init expects that user-data will be provided as base64 encoded value inside the text child of a element named `UserData` or `CustomData` which is a direct child of the `LinuxProvisioningConfigurationSet` (a sibling to `UserName`) If both `UserData` and `CustomData` are provided behavior is undefined on which will be selected.

In the example below, user-data provided is 'this is my userdata'

Example:

```
<wa:ProvisioningSection>
<wa:Version>1.0</wa:Version>
<LinuxProvisioningConfigurationSet
  xmlns="http://schemas.microsoft.com/windowsazure"
  xmlns:i="http://www.w3.org/2001/XMLSchema-instance">
  <ConfigurationSetType>LinuxProvisioningConfiguration</ConfigurationSetType>
  <HostName>myHost</HostName>
  <UserName>myuser</UserName>
  <UserPassword/>
  <CustomData>dGhpcyBpcyBteSB1c2VyZGF0YQ==</CustomData>
  <dscfg>eyJhZ2VudF9jb21tYW5kIjogWyJzdGFydCI6ICJ3YWxpbnV4YWdlbnQiXX0=</dscfg>
  <DisableSshPasswordAuthentication>true</DisableSshPasswordAuthentication>
  <SSH>
    <PublicKeys>
      <PublicKey>
        <Fingerprint>6BE7A7C3C8A8F4B123CCA5D0C2F1BE4CA7B63ED7</Fingerprint>
        <Path>this-value-unused</Path>
```

(continues on next page)

(continued from previous page)

```
</PublicKey>
</PublicKeys>
</SSH>
</LinuxProvisioningConfigurationSet>
</wa:ProvisioningSection>
```

hostname

When the user launches an instance, they provide a hostname for that instance. The hostname is provided to the instance in the `ovf-env.xml` file as `HostName`.

Whatever value the instance provides in its dhcp request will resolve in the domain returned in the ‘search’ request.

A generic image will already have a hostname configured. The ubuntu cloud images have ‘ubuntu’ as the hostname of the system, and the initial dhcp request on `eth0` is not guaranteed to occur after the `datasource` code has been run. So, on first boot, that initial value will be sent in the dhcp request and *that* value will resolve.

In order to make the `HostName` provided in the `ovf-env.xml` resolve, a dhcp request must be made with the new value. cloud-init handles this by setting the hostname in the `DataSource`’s ‘`get_data`’ method via ‘`hostname $HostName`’, and then bouncing the interface. This behavior can be configured or disabled in the `datasource` config. See ‘`Configuration`’ above.

CloudSigma

This `datasource` finds metadata and user-data from the [CloudSigma](#) cloud platform. Data transfer occurs through a virtual serial port of the [CloudSigma](#)’s VM and the presence of network adapter is **NOT** a requirement, See [server context](#) in the public documentation for more information.

Setting a hostname

By default the name of the server will be applied as a hostname on the first boot.

Providing user-data

You can provide user-data to the VM using the dedicated [meta field](#) in the [server context](#) `cloudinit-user-data`. By default *cloud-config* format is expected there and the `#cloud-config` header could be omitted. However since this is a raw-text field you could provide any of the valid [config formats](#).

You have the option to encode your user-data using Base64. In order to do that you have to add the `cloudinit-user-data` field to the `base64_fields`. The latter is a comma-separated field with all the meta fields with base64 encoded values.

If your user-data does not need an internet connection you can create a [meta field](#) in the [server context](#) `cloudinit-dsmode` and set “local” as value. If this field does not exist the default value is “net”.

CloudStack

Apache CloudStack expose user-data, meta-data, user password and account SSH key thru the Virtual-Router. The datasource obtains the VR address via dhcp lease information given to the instance. For more details on meta-data and user-data, refer the [CloudStack Administrator Guide](#).

URLs to access user-data and meta-data from the Virtual Machine. *data-server.* is a well-known hostname provided by the CloudStack virtual router that points to the next UserData server (which is usually also the virtual router).

```
http://data-server./latest/user-data
http://data-server./latest/meta-data
http://data-server./latest/meta-data/{metadata type}
```

If *data-server.* cannot be resolved, cloud-init will try to obtain the virtual router's address from the system's DHCP leases. If that fails, it will use the system's default gateway.

Configuration

The following configuration can be set for the datasource in system configuration (in */etc/cloud/cloud.cfg* or */etc/cloud/cloud.cfg.d/*).

The settings that may be configured are:

- **max_wait:** the maximum amount of clock time in seconds that should be spent searching *metadata_urls*. A value less than zero will result in only one request being made, to the first in the list. (default: 120)
- **timeout:** the timeout value provided to *urlopen* for each individual http request. This is used both when selecting a *metadata_url* and when crawling the metadata service. (default: 50)

An example configuration with the default values is provided below:

```
datasource:
  CloudStack:
    max_wait: 120
    timeout: 50
```

Config Drive

The configuration drive datasource supports the [OpenStack](#) configuration drive disk.

See the [config drive extension](#) and [metadata introduction](#) in the public documentation for more information.

By default, cloud-init does *always* consider this source to be a full-fledged datasource. Instead, the typical behavior is to assume it is really only present to provide networking information. Cloud-init will copy off the network information, apply it to the system, and then continue on. The “full” datasource could then be found in the EC2 metadata service. If this is not the case then the files contained on the located drive must provide equivalents to what the EC2 metadata service would provide (which is typical of the version 2 support listed below)

Version 1 (Deprecated)

Note: Version 1 is legacy and should be considered deprecated. Version 2 has been supported in OpenStack since 2012.2 (Folsom).

The following criteria are required to as a config drive:

1. Must be formatted with `vfat` filesystem
2. Must contain *one* of the following files

```
/etc/network/interfaces
/root/.ssh/authorized_keys
/meta.js
```

`/etc/network/interfaces`

This file is laid down by nova in order to pass static networking information to the guest. Cloud-init will copy it off of the config-drive and into `/etc/network/interfaces` (or convert it to RH format) as soon as it can, and then attempt to bring up all network interfaces.

`/root/.ssh/authorized_keys`

This file is laid down by nova, and contains the ssh keys that were provided to nova on instance creation (nova-boot -key ...).

`/meta.js`

meta.js is populated on the config-drive in response to the user passing “meta flags” (nova boot -meta key=value ...). It is expected to be json formatted.

Version 2

The following criteria are required to as a config drive:

1. Must be formatted with `vfat` or `iso9660` filesystem or have a *filesystem* label of **config-2** or **CONFIG-2**
2. The files that will typically be present in the config drive are:

```
openstack/
- 2012-08-10/ or latest/
- meta_data.json
- user_data (not mandatory)
- content/
- 0000 (referenced content files)
- 0001
- ....
ec2
- latest/
- meta-data.json (not mandatory)
```

Keys and values

Cloud-init's behavior can be modified by keys found in the meta.js (version 1 only) file in the following ways.

```
dsmode:
  values: local, net, pass
  default: pass
```

This is what indicates if configdrive is a final data source or not. By default it is 'pass', meaning this datasource should not be read. Set it to 'local' or 'net' to stop cloud-init from continuing on to search for other data sources after network config.

The difference between 'local' and 'net' is that local will not require networking to be up before user-data actions (or boothooks) are run.

```
instance-id:
  default: iid-dsconfigdrive
```

This is utilized as the metadata's instance-id. It should generally be unique, as it is what is used to determine "is this a new instance".

```
public-keys:
  default: None
```

If present, these keys will be used as the public keys for the instance. This value overrides the content in `authorized_keys`.

Note: it is likely preferable to provide keys via user-data

```
user-data:
  default: None
```

This provides cloud-init user-data. See [examples](#) for what all can be present here.

DigitalOcean

The [DigitalOcean](#) datasource consumes the content served from DigitalOcean's [metadata service](#). This metadata service serves information about the running droplet via HTTP over the link local address 169.254.169.254. The metadata API endpoints are fully described at <https://developers.digitalocean.com/metadata/>.

Configuration

DigitalOcean's datasource can be configured as follows:

datasource:

DigitalOcean:

retries: 3 timeout: 2

- *retries*: Determines the number of times to attempt to connect to the metadata service
- *timeout*: Determines the timeout in seconds to wait for a response from the metadata service

E24Cloud

E24Cloud platform provides an AWS Ec2 metadata service clone. It identifies itself to guests using the dmi system-manufacturer (/sys/class/dmi/id/sys_vendor).

Exoscale

This datasource supports reading from the metadata server used on the [Exoscale platform](#).

Use of the Exoscale datasource is recommended to benefit from new features of the Exoscale platform.

The datasource relies on the availability of a compatible metadata server (<http://169.254.169.254> is used by default) and its companion password server, reachable at the same address (by default on port 8080).

Crawling of metadata

The metadata service and password server are crawled slightly differently:

- The “metadata service” is crawled every boot.
- The password server is also crawled every boot (the Exoscale datasource forces the password module to run with “frequency always”).

In the password server case, the following rules apply in order to enable the “restore instance password” functionality:

- If a password is returned by the password server, it is then marked “saved” by the cloud-init datasource. Subsequent boots will skip setting the password (the password server will return “saved_password”).
- When the instance password is reset (via the Exoscale UI), the password server will return the non-empty password at next boot, therefore causing cloud-init to reset the instance’s password.

Configuration

Users of this datasource are discouraged from changing the default settings unless instructed to by Exoscale support.

The following settings are available and can be set for the *datasource base configuration* (in */etc/cloud/cloud.cfg.d/*).

The settings available are:

- **metadata_url**: The URL for the metadata service (defaults to <http://169.254.169.254>)
- **api_version**: The API version path on which to query the instance metadata (defaults to 1.0)
- **password_server_port**: The port (on the metadata server) on which the password server listens (defaults to 8080).
- **timeout**: the timeout value provided to urlopen for each individual http request. (defaults to 10)
- **retries**: The number of retries that should be done for an http request (defaults to 6)

An example configuration with the default values is provided below:

```
datasource:
  Exoscale:
    metadata_url: "http://169.254.169.254"
    api_version: "1.0"
    password_server_port: 8080
    timeout: 10
    retries: 6
```

Fallback/None

This is the fallback datasource when no other datasource can be selected. It is the equivalent of a empty datasource in that it provides a empty string as userdata and a empty dictionary as metadata. It is useful for testing as well as for when you do not have a need to have an actual datasource to meet your instance requirements (ie you just want to run modules that are not concerned with any external data). It is typically put at the end of the datasource search list so that if all other datasources are not matched, then this one will be so that the user is not left with an inaccessible instance.

Note: the instance id that this datasource provides is `iid-datasource-none`.

Google Compute Engine

The GCE datasource gets its data from the internal compute metadata server. Metadata can be queried at the URL `'http://metadata.google.internal/computeMetadata/v1/'` from within an instance. For more information see the [GCE metadata docs](#).

Currently the default project and instance level metadatakeys keys `project/attributes/sshKeys` and `instance/attributes/ssh-keys` are merged to provide `public-keys`.

`user-data` and `user-data-encoding` can be provided to cloud-init by setting those custom metadata keys for an *instance*.

Configuration

The following configuration can be set for the datasource in system configuration (in `/etc/cloud/cloud.cfg` or `/etc/cloud/cloud.cfg.d/`).

The settings that may be configured are:

- **retries:** The number of retries that should be done for an http request. This value is used only after `metadata_url` is selected. (default: 5)
- **sec_between_retries:** The amount of wait time between the retries when crawling the metadata service. (default: 1)

An example configuration with the default values is provided below:

```
datasource:
  GCE:
    retries: 5
    sec_between_retries: 1
```

LXD

The data source LXD allows the user to provide custom user-data, vendor-data, meta-data and network-config to the instance without running a network service (or even without having a network at all). This datasource performs HTTP GETs against the [LXD socket device](#) which is provided to each running LXD container and VM as `/dev/lxd/sock` and represents all instance-metadata as versioned HTTP routes such as:

- `1.0/meta-data`
- `1.0/config/user.meta-data`
- `1.0/config/user.vendor-data`
- `1.0/config/user.user-data`

- 1.0/config/user.<any-custom-key>

The LXD socket device `/dev/lxd/sock` is only present on containers and VMs when the instance configuration has `security.devlxd=true` (default). Disabling `security.devlxd` configuration setting at initial launch will ensure that cloud-init uses the *NoCloud* datasource. Disabling `security.devlxd` over the life of the container will result in warnings from cloud-init and cloud-init will keep the originally detected LXD datasource.

The LXD datasource is detected as viable by `ds-identify` during `systemd` generator time when either `/dev/lxd/sock` exists or `/sys/class/dmi/id/board_name` matches “LXD”.

The LXD datasource provides cloud-init the ability to react to meta-data, vendor-data, user-data and network-config changes and render the updated configuration across a system reboot.

To modify what meta-data, vendor-data or user-data are provided to the launched container, use either LXD profiles or `lxc launch ... -c <key>=<value>` at initial container launch setting one of the following keys:

- user.meta-data: YAML metadata which will be appended to base meta-data
- user.vendor-data: YAML which overrides any meta-data values
- user.network-config: YAML representing either *Networking Config Version 1* or *Networking Config Version 2* format
- user.user-data: YAML which takes preference and overrides both meta-data and vendor-data values
- user.any-key: Custom user configuration key and value pairs can be passed to cloud-init. Those keys/values will be present in instance-data which can be used by both *#template: jinja* *#cloud-config* templates and the *cloud-init query* command.

Note: LXD version 4.22 introduced a new scope of config keys prefaced by `cloud-init.` which are preferred above the related `user.*` keys:

- cloud-init.meta-data
- cloud-init.vendor-data
- cloud-init.network-config
- cloud-init.user-data

By default, network configuration from this datasource will be:

```
version: 1
config:
  - type: physical
    name: eth0
    subnets:
      - type: dhcp
        control: auto
```

This datasource is intended to replace *NoCloud* datasource for LXD instances with a more direct support for LXD APIs instead of static NoCloud seed files.

Hotplug

Network hotplug functionality is supported for the LXD datasource as described in the *Events and Updates* documentation. As hotplug functionality relies on the cloud provided network metadata, the LXD datasource will only meaningfully react to a hotplug event if it has the configuration necessary to respond to the change has been provided to LXD. Practically, this means that even with hotplug enabled, **the default behavior for adding a new virtual NIC will result no change.**

To update the configuration to be used by hotplug, first pass the network configuration via the `cloud-init.network-config` (or `user.network-config` on older versions).

For example, given an LXD instance named `my-lxd` with hotplug enabled and an LXD bridge named `my-bridge`, the following will allow for additional DHCP configuration of `eth1`:

```
$ cat /tmp/cloud-network-config.yaml
version: 2
ethernets:
  eth0:
    dhcp4: true
  eth1:
    dhcp4: true

$ lxc config set my-lxd cloud-init.network-config="$(cat /tmp/cloud-network-config.yaml)"
$ lxc config device add my-lxd eth1 nic name=eth1 nictype=bridged parent=my-bridge
Device eth1 added to my-lxd
```

MAAS

For now see: <https://maas.io/docs>

NoCloud

The data source NoCloud allows the user to provide user-data and meta-data to the instance without running a network service (or even without having a network at all).

You can provide meta-data and user-data to a local vm boot via files on a `vfat` or `iso9660` filesystem. The filesystem volume label must be `cidata` or `CIDATA`.

Alternatively, you can provide meta-data via kernel command line or SMBIOS “serial number” option. The data must be passed in the form of a string:

```
ds=nocloud[;key=val;key=val]
```

or

```
ds=nocloud-net[;key=val;key=val]
```

The permitted keys are:

- `h` or `local-hostname`
- `i` or `instance-id`
- `s` or `seedfrom`

With `ds=nocloud`, the `seedfrom` value must start with `/` or `file://`. With `ds=nocloud-net`, the `seedfrom` value must start with `http://` or `https://`.

e.g. you can pass this option to QEMU:

```
-smbios type=1,serial=ds=nocloud-net;s=http://10.10.0.1:8000/
```

to cause NoCloud to fetch the full meta-data from <http://10.10.0.1:8000/meta-data> after the network initialization is complete.

These user-data and meta-data files are expected to be in the following format.

```
/user-data
/meta-data
```

Both files are required to be present for it to be considered a valid seed ISO.

Basically, user-data is simply user-data and meta-data is a YAML formatted file representing what you'd find in the EC2 metadata service.

You may also optionally provide a vendor-data file in the following format.

```
/vendor-data
```

Given a disk ubuntu cloud image in 'disk.img', you can create a sufficient disk by following the example below.

```
## 1) create user-data and meta-data files that will be used
## to modify image on first boot
$ echo -e "instance-id: iid-local01\nlocal-hostname: cloudimg" > meta-data
$ echo -e "#cloud-config\npassword: passw0rd\nchpasswd: { expire: False }\nssh_pwauth: \
↪True\n" > user-data

## 2a) create a disk to attach with some user-data and meta-data
$ genisoimage -output seed.iso -volid cidata -joliet -rock user-data meta-data

## 2b) alternatively, create a vfat filesystem with same files
## $ truncate --size 2M seed.iso
## $ mkfs.vfat -n cidata seed.iso

## 2b) option 1: mount and copy files
## $ sudo mount -t vfat seed.iso /mnt
## $ sudo cp user-data meta-data /mnt
## $ sudo umount /mnt

## 2b) option 2: the mtools package provides mcopy, which can access vfat
## filesystems without mounting them
## $ mcopy -oi seed.iso user-data meta-data

## 3) create a new qcow image to boot, backed by your original image
$ qemu-img create -f qcow2 -b disk.img -F qcow2 boot-disk.img

## 4) boot the image and login as 'ubuntu' with password 'passw0rd'
## note, passw0rd was set as password through the user-data above,
## there is no password set on these images.
$ kvm -m 256 \
    -net nic -net user,hostfwd=tcp::2222-:22 \
```

(continues on next page)

(continued from previous page)

```
-drive file=boot-disk.img,if=virtio \
-drive driver=raw,file=seed.iso,if=virtio
```

Note: that the instance-id provided (iid-local01 above) is what is used to determine if this is “first boot”. So if you are making updates to user-data you will also have to change that, or start the disk fresh.

Also, you can inject an `/etc/network/interfaces` file by providing the content for that file in the `network-interfaces` field of metadata.

Example metadata:

```
instance-id: iid-abcdefg
network-interfaces: |
  iface eth0 inet static
  address 192.168.1.10
  network 192.168.1.0
  netmask 255.255.255.0
  broadcast 192.168.1.255
  gateway 192.168.1.254
hostname: myhost
```

Network configuration can also be provided to cloud-init in either *Networking Config Version 1* or *Networking Config Version 2* by providing that YAML formatted data in a file named `network-config`. If found, this file will override a `network-interfaces` file.

See an example below. Note specifically that this file does not have a top level `network` key as it is already assumed to be network configuration based on the filename.

```
version: 1
config:
  - type: physical
    name: interface0
    mac_address: "52:54:00:12:34:00"
    subnets:
      - type: static
        address: 192.168.1.10
        netmask: 255.255.255.0
        gateway: 192.168.1.254
```

```
version: 2
ethernets:
  interface0:
    match:
      macaddress: "52:54:00:12:34:00"
    set-name: interface0
    addresses:
      - 192.168.1.10/255.255.255.0
    gateway4: 192.168.1.254
```

OpenNebula

The [OpenNebula](#) (ON) datasource supports the contextualization disk.

See [contextualization overview](#), [contextualizing VMs](#) and [network configuration](#) in the public documentation for more information.

OpenNebula's virtual machines are contextualized (parametrized) by CD-ROM image, which contains a shell script *context.sh* with custom variables defined on virtual machine start. There are no fixed contextualization variables, but the datasource accepts many used and recommended across the documentation.

Datasource configuration

Datasource accepts following configuration options.

```
dsmode:
  values: local, net, disabled
  default: net
```

Tells if this datasource will be processed in 'local' (pre-networking) or 'net' (post-networking) stage or even completely 'disabled'.

```
parseuser:
  default: nobody
```

Unprivileged system user used for contextualization script processing.

Contextualization disk

The following criteria are required:

1. Must be formatted with [iso9660](#) filesystem or have a *filesystem* label of **CONTEXT** or **CDROM**
2. Must contain file *context.sh* with contextualization variables. File is generated by OpenNebula, it has a KEY='VALUE' format and can be easily read by bash

Contextualization variables

There are no fixed contextualization variables in OpenNebula, no standard. Following variables were found on various places and revisions of the OpenNebula documentation. Where multiple similar variables are specified, only first found is taken.

```
DSMODE
```

Datasource mode configuration override. Values: local, net, disabled.

```
DNS
ETH<x>_IP
ETH<x>_NETWORK
ETH<x>_MASK
ETH<x>_GATEWAY
ETH<x>_GATEWAY6
ETH<x>_DOMAIN
```

(continues on next page)

(continued from previous page)

```

ETH<x>_DNS
ETH<x>_SEARCH_DOMAIN
ETH<x>_MTU
ETH<x>_IP6
ETH<x>_IP6_ULA
ETH<x>_IP6_PREFIX_LENGTH
ETH<x>_IP6_GATEWAY

```

Static [network configuration](#).

```

SET_HOSTNAME
HOSTNAME

```

Instance hostname.

```

PUBLIC_IP
IP_PUBLIC
ETH0_IP

```

If no hostname has been specified, cloud-init will try to create hostname from instance's IP address in 'local' dsmode. In 'net' dsmode, cloud-init tries to resolve one of its IP addresses to get hostname.

```

SSH_KEY
SSH_PUBLIC_KEY

```

One or multiple SSH keys (separated by newlines) can be specified.

```

USER_DATA
USERDATA

```

cloud-init user data.

Example configuration

This example cloud-init configuration (*cloud.cfg*) enables OpenNebula datasource only in 'net' mode.

```

disable_ec2_metadata: True
datasource_list: ['OpenNebula']
datasource:
  OpenNebula:
    dsmode: net
    parseuser: nobody

```

Example VM's context section

```
CONTEXT=[
    SSH_KEY="$USER[SSH_KEY]
$USER[SSH_KEY1]
$USER[SSH_KEY2]",
    PUBLIC_IP="$NIC[IP]",
    USER_DATA="#cloud-config
# see https://help.ubuntu.com/community/CloudInit

packages: []

mounts:
- [vdc,none,swap,sw,0,0]
runcmd:
- echo 'Instance has been configured by cloud-init.' | wall
"]
```

OpenStack

This datasource supports reading data from the [OpenStack Metadata Service](#).

Discovery

To determine whether a platform looks like it may be OpenStack, cloud-init checks the following environment attributes as a potential OpenStack platform:

- Maybe OpenStack if:
 - **non-x86 cpu architecture**: because DMI data is buggy on some arches
- Is OpenStack **if x86 architecture and ANY** of the following:
 - **/proc/1/environ**: Nova-lxd contains *product_name=OpenStack Nova*
 - **DMI product_name**: Either *Openstack Nova* or *OpenStack Compute*
 - **DMI chassis_asset_tag** is *HUAWEICLOUD*, *OpenTelekomCloud*, *SAP CCloud VM*, *OpenStack Nova* (since 19.2) or *OpenStack Compute* (since 19.2)

Configuration

The following configuration can be set for the datasource in system configuration (in */etc/cloud/cloud.cfg* or */etc/cloud/cloud.cfg.d/*).

The settings that may be configured are:

- **metadata_urls**: This list of urls will be searched for an OpenStack metadata service. The first entry that successfully returns a 200 response for `<url>/openstack` will be selected. (default: [`'http://169.254.169.254'`])
- **max_wait**: the maximum amount of clock time in seconds that should be spent searching `metadata_urls`. A value less than zero will result in only one request being made, to the first in the list. (default: -1)
- **timeout**: the timeout value provided to `urlopen` for each individual http request. This is used both when selecting a `metadata_url` and when crawling the metadata service. (default: 10)

- **retries:** The number of retries that should be done for an http request. This value is used only after `metadata_url` is selected. (default: 5)
- **apply_network_config:** A boolean specifying whether to configure the network for the instance based on `network_data.json` provided by the metadata service. When False, only configure dhcp on the primary nic for this instances. (default: True)

An example configuration with the default values is provided below:

```
datasource:
  OpenStack:
    metadata_urls: ["http://169.254.169.254"]
    max_wait: -1
    timeout: 10
    retries: 5
    apply_network_config: True
```

Vendor Data

The OpenStack metadata server can be configured to serve up vendor data which is available to all instances for consumption. OpenStack vendor data is, generally, a JSON object.

cloud-init will look for configuration in the `cloud-init` attribute of the vendor data JSON object. cloud-init processes this configuration using the same handlers as user data, so any formats that work for user data should work for vendor data.

For example, configuring the following as vendor data in OpenStack would upgrade packages and install `htop` on all instances:

```
{"cloud-init": "#cloud-config\npackage_upgrade: True\npackages:\n - htop"}
```

For more general information about how cloud-init handles vendor data, including how it can be disabled by users on instances, see [Vendor Data](#).

OpenStack can also be configured to provide ‘dynamic vendordata’ which is provided by the DynamicJSON provider and appears under a different metadata path, `/vendor_data2.json`.

Cloud-init will look for a `cloud-init` at the `vendor_data2` path; if found, settings are applied after (and, hence, overriding) the settings from static vendor data. Both sets of vendor data can be overridden by user data.

Oracle

This datasource reads metadata, vendor-data and user-data from [Oracle Compute Infrastructure \(OCI\)](#).

Oracle Platform

OCI provides bare metal and virtual machines. In both cases, the platform identifies itself via DMI data in the chassis asset tag with the string ‘OracleCloud.com’.

Oracle’s platform provides a metadata service that mimics the 2013-10-17 version of OpenStack metadata service. Initially support for Oracle was done via the OpenStack datasource.

Cloud-init has a specific datasource for Oracle in order to:

- allow and support future growth of the OCI platform.

- b. address small differences between OpenStack and Oracle metadata implementation.

Configuration

The following configuration can be set for the datasource in system configuration (in `/etc/cloud/cloud.cfg` or `/etc/cloud/cloud.cfg.d/`).

The settings that may be configured are:

- **configure_secondary_nics**: A boolean, defaulting to False. If set to True on an OCI Virtual Machine, cloud-init will fetch networking metadata from Oracle's IMDS and use it to configure the non-primary network interface controllers in the system. If set to True on an OCI Bare Metal Machine, it will have no effect (though this may change in the future).

An example configuration with the default values is provided below:

```
datasource:  
  Oracle:  
    configure_secondary_nics: false
```

OVF

The OVF Datasource provides a datasource for reading data from on an [Open Virtualization Format](#) ISO transport.

For further information see a full working example in cloud-init's source code tree in `doc/sources/ovf`

Configuration

The following configuration can be set for the datasource in system configuration (in `/etc/cloud/cloud.cfg` or `/etc/cloud/cloud.cfg.d/`).

The settings that may be configured are:

- **disable_vmware_customization**: disable or enable the vmware customization based on vmware customization files. (default: True)
- **allow_raw_data**: enable or disable the vmware customization based on raw cloud-init data including metadata and userdata. (default: True)
- **vmware_cust_file_max_wait**: the maximum amount of clock time in seconds that should be spent waiting for vmware customization files. (default: 15)

On VMware platforms, VMTools use is required for OVF datasource configuration settings as well as vCloud and vSphere admin configuration. User could change the VMTools configuration options with command:

```
vmware-toolbox-cmd config set <section> <key> <value>
```

The following VMTools configuration options affect cloud-init's behavior on a booted VM:

- **a: [deploypkg] enable-custom-scripts**

If this option is absent in VMTools configuration, the custom script is disabled by default for security reasons. Some VMware products could change this default behavior (for example: enabled by default) via customization specification settings.

VMWare admin can refer to (<https://github.com/canonical/cloud-init/blob/main/cloudinit/sources/helpers/vmware/imc/config.py>) and set the customization specification settings.

For more information, see [VMware vSphere Product Documentation](#) and specific VMTools parameters consumed.

Rbx Cloud

The Rbx datasource consumes the metadata drive available on platform [HyperOne](#) and [Rootbox](#) platform.

Datasource supports, in particular, network configurations, hostname, user accounts and user metadata.

Metadata drive

Drive metadata is a [FAT](#)-formatted partition with the ``CLOUDMD`` or ``cloudmd`` label on the system disk. Its contents are refreshed each time the virtual machine is restarted, if the partition exists. For more information see [HyperOne Virtual Machine docs](#).

SmartOS Datasource

This datasource finds metadata and user-data from the SmartOS virtualization platform (i.e. Joyent).

Please see <http://smartos.org/> for information about SmartOS.

SmartOS Platform

The SmartOS virtualization platform uses meta-data to the instance via the second serial console. On Linux, this is `/dev/ttyS1`. The data is provided via a simple protocol: something queries for the data, the console responds with the status and if “SUCCESS” returns until a single “`\n`”.

New versions of the SmartOS tooling will include support for base64 encoded data.

Meta-data channels

Cloud-init supports three modes of delivering user/meta-data via the flexible channels of SmartOS.

- user-data is written to `/var/db/user-data`
 - per the spec, user-data is for consumption by the end-user, not provisioning tools
 - cloud-init entirely ignores this channel other than writing it to disk
 - removal of the meta-data key means that `/var/db/user-data` gets removed
 - a backup of previous meta-data is maintained as `/var/db/user-data.<timestamp>`. `<timestamp>` is the epoch time when cloud-init ran
- user-script is written to `/var/lib/cloud/scripts/per-boot/99_user_data`
 - this is executed each boot
 - a link is created to `/var/db/user-script`
 - previous versions of the user-script is written to `/var/lib/cloud/scripts/per-boot.backup/99_user_script.<timestamp>`. - `<timestamp>` is the epoch time when cloud-init ran.
 - when the ‘user-script’ meta-data key goes missing, the user-script is removed from the file system, although a backup is maintained.
 - if the script does not start with a shebang (i.e. starts with `#!<executable>`), then or is not an executable, cloud-init will add a shebang of `“#!/bin/bash”`

- cloud-init:user-data is treated like on other Clouds.
 - this channel is used for delivering `_all_` cloud-init instructions
 - scripts delivered over this channel must be well formed (i.e. must have a shebang)

Cloud-init supports reading the traditional meta-data fields supported by the SmartOS tools. These are:

- `root_authorized_keys`
- `hostname`
- `enable_motd_sys_info`
- `iptables_disable`

Note: At this time `iptables_disable` and `enable_motd_sys_info` are read but are not actioned.

Disabling user-script

Cloud-init uses the per-boot script functionality to handle the execution of the user-script. If you want to prevent this use a cloud-config of:

```
#cloud-config
cloud_final_modules:
- scripts-per-once
- scripts-per-instance
- scripts-user
- ssh-authkey-fingerprints
- keys-to-console
- phone-home
- final-message
- power-state-change
```

Alternatively you can use the json patch method

```
#cloud-config-jsonp
[
  {
    "op": "replace",
    "path": "/cloud_final_modules",
    "value": [
      "scripts-per-once",
      "scripts-per-instance",
      "scripts-user",
      "ssh-authkey-fingerprints",
      "keys-to-console",
      "phone-home",
      "final-message",
      "power-state-change"
    ]
  }
]
```

The default cloud-config includes “script-per-boot”. Cloud-init will still ingest and write the user-data but will not execute it, when you disable the per-boot script handling.

Note: Unless you have an explicit use-case, it is recommended that you not disable the per-boot script execution, especially if you are using any of the life-cycle management features of SmartOS.

The cloud-config needs to be delivered over the cloud-init:user-data channel in order for cloud-init to ingest it.

base64

The following are exempt from base64 encoding, owing to the fact that they are provided by SmartOS:

- root_authorized_keys
- enable_motd_sys_info
- iptables_disable
- user-data
- user-script

This list can be changed through *datasource base configuration* variable 'no_base64_decode'.

This means that user-script and user-data as well as other values can be base64 encoded. Since Cloud-init can only guess as to whether or not something is truly base64 encoded, the following meta-data keys are hints as to whether or not to base64 decode something:

- base64_all: Except for excluded keys, attempt to base64 decode the values. If the value fails to decode properly, it will be returned in its text
- base64_keys: A comma delimited list of which keys are base64 encoded.
- b64-<key>: for any key, if there exists an entry in the metadata for 'b64-<key>' Then 'b64-<key>' is expected to be a plaintext boolean indicating whether or not its value is encoded.
- no_base64_decode: This is a configuration setting (i.e. /etc/cloud/cloud.cfg.d) that sets which values should not be base64 decoded.

disk_aliases and ephemeral disk

By default, SmartOS only supports a single ephemeral disk. That disk is completely empty (un-partitioned with no filesystem).

The SmartOS datasource has built-in cloud-config which instructs the 'disk_setup' module to partition and format the ephemeral disk.

You can control the disk_setup then in 2 ways:

1. through the datasource config, you can change the 'alias' of ephemeral0 to reference another device. The default is:

```
'disk_aliases': {'ephemeral0': '/dev/vdb'},
```

Which means anywhere disk_setup sees a device named 'ephemeral0' then /dev/vdb will be substituted.

2. you can provide disk_setup or fs_setup data in user-data to overwrite the datasource's built-in values.

See doc/examples/cloud-config-disk-setup.txt for information on disk_setup.

UpCloud

The **UpCloud** datasource consumes information from UpCloud's **metadata service**. This metadata service serves information about the running server via HTTP over the address 169.254.169.254 available in every DHCP-configured interface. The metadata API endpoints are fully described in UpCloud API documentation at <https://developers.upcloud.com/1.3/8-servers/#metadata-service>.

Providing user-data

When creating a server, user-data is provided by specifying it as *user_data* in the API or via the server creation tool in the control panel. User-data is immutable during server's lifetime and can be removed by deleting the server.

VMware

This datasource is for use with systems running on a VMware platform such as vSphere and currently supports the following data transports:

- **GuestInfo** keys

Configuration

The configuration method is dependent upon the transport:

GuestInfo Keys

One method of providing meta, user, and vendor data is by setting the following key/value pairs on a VM's `extraConfig` property:

Property	Description
<code>guestinfo.metadata</code>	A YAML or JSON document containing the cloud-init metadata.
<code>guestinfo.metadata.encoding</code>	The encoding type for <code>guestinfo.metadata</code> .
<code>guestinfo.userdata</code>	A YAML document containing the cloud-init user data.
<code>guestinfo.userdata.encoding</code>	The encoding type for <code>guestinfo.userdata</code> .
<code>guestinfo.vendordata</code>	A YAML document containing the cloud-init vendor data.
<code>guestinfo.vendordata.encoding</code>	The encoding type for <code>guestinfo.vendordata</code> .

All `guestinfo.*.encoding` values may be set to `base64` or `gzip+base64`.

Features

This section reviews several features available in this datasource, regardless of how the meta, user, and vendor data was discovered.

Instance data and lazy networks

One of the hallmarks of cloud-init is [its use of instance-data and JINJA queries](#) – the ability to write queries in user and vendor data that reference runtime information present in `/run/cloud-init/instance-data.json`. This works well when the metadata provides all of the information up front, such as the network configuration. For systems that rely on DHCP, however, this information may not be available when the metadata is persisted to disk.

This datasource ensures that even if the instance is using DHCP to configure networking, the same details about the configured network are available in `/run/cloud-init/instance-data.json` as if static networking was used. This information collected at runtime is easy to demonstrate by executing the datasource on the command line. From the root of this repository, run the following command:

```
PYTHONPATH="$(pwd)" python3 cloudinit/sources/DataSourceVMware.py
```

The above command will result in output similar to the below JSON:

```
{
  "hostname": "akutz.localhost",
  "local-hostname": "akutz.localhost",
  "local-ipv4": "192.168.0.188",
  "local_hostname": "akutz.localhost",
  "network": {
    "config": {
      "dhcp": true
    },
    "interfaces": {
      "by-ipv4": {
        "172.0.0.2": {
          "netmask": "255.255.255.255",
          "peer": "172.0.0.2"
        },
        "192.168.0.188": {
          "broadcast": "192.168.0.255",
          "mac": "64:4b:f0:18:9a:21",
          "netmask": "255.255.255.0"
        }
      },
      "by-ipv6": {
        "fd8e:d25e:c5b6:1:1f5:b2fd:8973:22f2": {
          "flags": 208,
          "mac": "64:4b:f0:18:9a:21",
          "netmask": "ffff:ffff:ffff:ffff::/64"
        }
      },
      "by-mac": {
        "64:4b:f0:18:9a:21": {
          "ipv4": [
            {
              "addr": "192.168.0.188",
              "broadcast": "192.168.0.255",
              "netmask": "255.255.255.0"
            }
          ],
          "ipv6": [
```

(continues on next page)

(continued from previous page)

```

        {
            "addr": "fd8e:d25e:c5b6:1:1f5:b2fd:8973:22f2",
            "flags": 208,
            "netmask": "ffff:ffff:ffff:ffff:~/64"
        }
    ],
    "ac:de:48:00:11:22": {
        "ipv6": []
    }
}
},
"wait-on-network": {
    "ipv4": true,
    "ipv6": "false"
}
}

```

Redacting sensitive information

Sometimes the cloud-init userdata might contain sensitive information, and it may be desirable to have the `guestinfo` userdata key (or other `guestinfo` keys) redacted as soon as its data is read by the datasource. This is possible by adding the following to the metadata:

```

redact: # formerly named cleanup-guestinfo, which will also work
- userdata
- vendordata

```

When the above snippet is added to the metadata, the datasource will iterate over the elements in the `redact` array and clear each of the keys. For example, when the `guestinfo` transport is used, the above snippet will cause the following commands to be executed:

```

vmware-rpctool "info-set guestinfo.userdata ---"
vmware-rpctool "info-set guestinfo.userdata.encoding "
vmware-rpctool "info-set guestinfo.vendordata ---"
vmware-rpctool "info-set guestinfo.vendordata.encoding "

```

Please note that keys are set to the valid YAML string `---` as it is not possible to remove an existing key from the `guestinfo` key-space. A key's analogous encoding property will be set to a single white-space character, causing the datasource to treat the actual key value as plain-text, thereby loading it as an empty YAML doc (hence the aforementioned `---`).

Reading the local IP addresses

This datasource automatically discovers the local IPv4 and IPv6 addresses for a guest operating system based on the default routes. However, when inspecting a VM externally, it's not possible to know what the *default* IP address is for the guest OS. That's why this datasource sets the discovered, local IPv4 and IPv6 addresses back in the `guestinfo` namespace as the following keys:

- `guestinfo.local-ipv4`
- `guestinfo.local-ipv6`

It is possible that a host may not have any default, local IP addresses. It's also possible the reported, local addresses are link-local addresses. But these two keys may be used to discover what this datasource determined were the local IPv4 and IPv6 addresses for a host.

Waiting on the network

Sometimes cloud-init may bring up the network, but it will not finish coming online before the datasource's `setup` function is called, resulting in an `/var/run/cloud-init/instance-data.json` file that does not have the correct network information. It is possible to instruct the datasource to wait until an IPv4 or IPv6 address is available before writing the instance data with the following metadata properties:

```
wait-on-network:
  ipv4: true
  ipv6: true
```

If either of the above values are true, then the datasource will sleep for a second, check the network status, and repeat until one or both addresses from the specified families are available.

Walkthrough

The following series of steps is a demonstration on how to configure a VM with this datasource:

1. Create the metadata file for the VM. Save the following YAML to a file named `metadata.yaml`:

```
instance-id: cloud-vm
local-hostname: cloud-vm
network:
  version: 2
  ethernets:
    nics:
      match:
        name: ens*
      dhcp4: yes
```

2. Create the userdata file `userdata.yaml`:

```
#cloud-config

users:
- default
- name: akutz
  primary_group: akutz
```

(continues on next page)

(continued from previous page)

```

sudo: ALL=(ALL) NOPASSWD:ALL
groups: sudo, wheel
lock_passwd: true
ssh_authorized_keys:
- ssh-rsa AAAAB3NzaC1yc2EAAAADAQABAAQDE0c5FczvcGSh/tG4iw+Fhfi/05/EvUM/
→ 96js65tly4++YTXK1d9jcznPS5ruDlbIZ30oveCBd3kT8LLVfwzh6hepYTF0YmCTpF4eDunyqmpCXDvVscQYRXyasEm5olGmV
→ mt2PcPjooeX00vAj81jjU2f3XKrjz2u2+KI t9eba+v0Q6HiC8c2IzRkUAJ5i1atLy8RIbejo23+0P4N2jjk17QySF0VHwPBI
→ 0M/4ideeU74EN/
→ CgVsv06JrLsPBR4dojkV5qNbMNxIVv5cUwIy2ThlLgqpNCeFIDLWNZEfKlEuNeSQ2mPtI07ETxEL2Cz5y/
→ 7AIuildzYMc6wi2bofRC8HmQ7rMXRWdWlKWsR0L7SKjHblIwarxOGqLnUI+k2E71YoP7SZS1xaKi17pqkr00MCF+kKqvcvHA
→ tZKSpjYtjMb5+RonfhaFRNzv7cCE1f3Kp8UVqAdcGBTtReoE8eRUT63qIxjw03a7VwAyB2w+9cu1R9/
→ vAo8SBeRqw== sakutz@gmail.com

```

- Please note this step requires that the VM be powered off. All of the commands below use the VMware CLI tool, `govc`.

Go ahead and assign the path to the VM to the environment variable `VM`:

```
export VM="/inventory/path/to/the/vm"
```

- Power off the VM:

To ensure the next power-on operation results in a first-boot scenario for cloud-init, it may be necessary to run the following command just before powering off the VM:

```
cloud-init clean --logs --machine-id
```

Otherwise cloud-init may not run in first-boot mode. For more information on how the boot mode is determined, please see the [First Boot Documentation](#).

```
govc vm.power -off "${VM}"
```

- Export the environment variables that contain the cloud-init metadata and userdata:

```
export METADATA=$(gzip -c9 <metadata.yaml | { base64 -w0 2>/dev/null || base64; }) \
USERDATA=$(gzip -c9 <userdata.yaml | { base64 -w0 2>/dev/null || base64; })
```

- Assign the metadata and userdata to the VM:

```
govc vm.change -vm "${VM}" \
-e guestinfo.metadata="${METADATA}" \
-e guestinfo.metadata.encoding="gzip+base64" \
-e guestinfo.userdata="${USERDATA}" \
-e guestinfo.userdata.encoding="gzip+base64"
```

Please note the above commands include specifying the encoding for the properties. This is important as it informs the datasource how to decode the data for cloud-init. Valid values for `metadata.encoding` and `userdata.encoding` include:

- `base64`
- `gzip+base64`

- Power on the VM:

```
govc vm.power -on "${VM}"
```

If all went according to plan, the CentOS box is:

- Locked down, allowing SSH access only for the user in the userdata
- Configured for a dynamic IP address via DHCP
- Has a hostname of `cloud-vm`

Examples

This section reviews common configurations:

Setting the hostname

The hostname is set by way of the metadata key `local-hostname`.

Setting the instance ID

The instance ID may be set by way of the metadata key `instance-id`. However, if this value is absent then the instance ID is read from the file `/sys/class/dmi/id/product_uuid`.

Providing public SSH keys

The public SSH keys may be set by way of the metadata key `public-keys-data`. Each newline-terminated string will be interpreted as a separate SSH public key, which will be placed in distro's default user's `~/.ssh/authorized_keys`. If the value is empty or absent, then nothing will be written to `~/.ssh/authorized_keys`.

Configuring the network

The network is configured by setting the metadata key `network` with a value consistent with Network Config Versions 1 or 2, depending on the Linux distro's version of cloud-init.

The metadata key `network.encoding` may be used to indicate the format of the metadata key "network". Valid encodings are `base64` and `gzip+base64`.

Vultr

The [Vultr](#) datasource retrieves basic configuration values from the locally accessible [metadata service](#). All data is served over HTTP from the address `169.254.169.254`. The endpoints are documented in <https://www.vultr.com/metadata/>

Configuration

Vultr's datasource can be configured as follows:

datasource:

Vultr:

url: 'http://169.254.169.254' retries: 3 timeout: 2 wait: 2

- *url*: The URL used to acquire the metadata configuration from
- *retries*: Determines the number of times to attempt to connect to the metadata service
- *timeout*: Determines the timeout in seconds to wait for a response from the metadata service
- *wait*: Determines the timeout in seconds to wait before retrying after accessible failure

ZStack

ZStack platform provides a AWS Ec2 metadata service, but with different datasource identity. More information about ZStack can be found at [ZStack](#).

Discovery

To determine whether a vm running on ZStack platform, cloud-init checks DMI information by 'dmidecode -s chassis-asset-tag', if the output ends with '.zstack.io', it's running on ZStack platform:

Metadata

Same as EC2, instance metadata can be queried at

```
GET http://169.254.169.254/2009-04-04/meta-data/  
instance-id  
local-hostname
```

Userdata

Same as EC2, instance userdata can be queried at

```
GET http://169.254.169.254/2009-04-04/user-data/  
meta_data.json  
user_data  
password
```


NWCS

The NWCS datasource retrieves basic configuration values from the locally accessible metadata service. All data is served over HTTP from the address 169.254.169.254.

Configuration

NWCS' datasource can be configured as follows:

datasource:

NWCS:

url: 'http://169.254.169.254' retries: 3 timeout: 2 wait: 2

- *url*: The URL used to acquire the metadata configuration from
- *retries*: Determines the number of times to attempt to connect to the metadata service
- *timeout*: Determines the timeout in seconds to wait for a response from the metadata service
- *wait*: Determines the timeout in seconds to wait before retrying after accessible failure

2.13.2 Creation

The datasource objects have a few touch points with cloud-init. If you are interested in adding a new datasource for your cloud platform you will need to take care of the following items:

- **Identify a mechanism for positive identification of the platform:** It is good practice for a cloud platform to positively identify itself to the guest. This allows the guest to make educated decisions based on the platform on which it is running. On the x86 and arm64 architectures, many clouds identify themselves through DMI data. For example, Oracle's public cloud provides the string 'OracleCloud.com' in the DMI chassis-asset field.

cloud-init enabled images produce a log file with details about the platform. Reading through this log in `/run/cloud-init/ds-identify.log` may provide the information needed to uniquely identify the platform. If the log is not present, you can generate it by running from source `./tools/ds-identify` or the installed location `/usr/lib/cloud-init/ds-identify`.

The mechanism used to identify the platform will be required for the ds-identify and datasource module sections below.

- **Add datasource module ``cloudinit/sources/DataSource<CloudPlatform>.py``:** It is suggested that you start by copying one of the simpler datasources such as `DataSourceHetzner`.
- **Add tests for datasource module:** Add a new file with some tests for the module to `cloudinit/sources/test_<yourplatform>.py`. For example see `cloudinit/sources/tests/test_oracle.py`
- **Update ds-identify:** In systemd systems, ds-identify is used to detect which datasource should be enabled or if cloud-init should run at all. You'll need to make changes to `tools/ds-identify`.
- **Add tests for ds-identify:** Add relevant tests in a new class to `tests/unittests/test_ds_identify.py`. You can use `TestOracle` as an example.
- **Add your datasource name to the builtin list of datasources:** Add your datasource module name to the end of the `datasource_list` entry in `cloudinit/settings.py`.
- **Add your cloud platform to apport collection prompts:** Update the list of cloud platforms in `cloudinit/apport.py`. This list will be provided to the user who invokes `ubuntu-bug cloud-init`.

- **Enable datasource by default in ubuntu packaging branches:** Ubuntu packaging branches contain a template file `debian/cloud-init.templates` that ultimately sets the default `datasource_list` when installed via package. This file needs updating when the commit gets into a package.
- **Add documentation for your datasource:** You should add a new file in `doc/datasources/<cloudplatform>.rst`

2.14 Vendor Data

2.14.1 Overview

Vendordata is data provided by the entity that launches an instance (for example, the cloud provider). This data can be used to customize the image to fit into the particular environment it is being run in.

Vendordata follows the same rules as user-data, with the following caveats:

1. Users have ultimate control over vendordata. They can disable its execution or disable handling of specific parts of multipart input.
2. By default it only runs on first boot
3. Vendordata can be disabled by the user. If the use of vendordata is required for the instance to run, then vendordata should not be used.
4. user supplied cloud-config is merged over cloud-config from vendordata.

Users providing cloud-config data can use the ‘`#cloud-config-jsonp`’ method to more finely control their modifications to the vendor supplied cloud-config. For example, if both vendor and user have provided ‘`runcmd`’ then the default merge handler will cause the user’s `runcmd` to override the one provided by the vendor. To append to ‘`runcmd`’, the user could better provide multipart input with a cloud-config-jsonp part like:

```
#cloud-config-jsonp
[{"op": "add", "path": "/runcmd", "value": ["my", "command", "here"]}]
```

Further, we strongly advise vendors to not ‘be evil’. By evil, we mean any action that could compromise a system. Since users trust you, please take care to make sure that any vendordata is safe, atomic, idempotent and does not put your users at risk.

2.14.2 Input Formats

cloud-init will download and cache to filesystem any vendor-data that it finds. Vendordata is handled exactly like user-data. That means that the vendor can supply multipart input and have those parts acted on in the same way as user-data.

The only differences are:

- vendor-data-defined scripts are stored in a different location than user-data-defined scripts (to avoid namespace collision)
- user can disable part handlers by cloud-config settings. For example, to disable handling of ‘part-handlers’ in vendor-data, the user could provide user-data like this:

```
#cloud-config
vendordata: {excluded: 'text/part-handler'}
```

2.14.3 Examples

There are examples in the examples subdirectory.

Additionally, the ‘tools’ directory contains ‘write-mime-multipart’, which can be used to easily generate mime-multi-part files from a list of input files. That data can then be given to an instance.

See ‘write-mime-multipart –help’ for usage.

2.15 Network Configuration

- Default Behavior
- Disabling Network Configuration
- Fallback Networking
- Network Configuration Sources
- Network Configuration Outputs
- Network Output Policy
- Network Configuration Tools
- Examples

2.15.1 Default Behavior

Cloud-init ‘s searches for network configuration in order of increasing precedence; each item overriding the previous.

Datasource

For example, OpenStack may provide network config in the MetaData Service.

System Config

A `network:` entry in `/etc/cloud/cloud.cfg.d/*` configuration files.

Kernel Command Line

`ip=` or `network-config=<Base64 encoded YAML config string>`

User-data cannot change an instance’s network configuration. In the absence of network configuration in any of the above sources, Cloud-init will write out a network configuration that will issue a DHCP request on a “first” network interface.

Note: The network-config value is expected to be a Base64 encoded YAML string in *Networking Config Version 1* or *Networking Config Version 2* format. Optionally it can be compressed with `gzip` prior to Base64 encoding.

2.15.2 Disabling Network Configuration

Users may disable `Cloud-init` 's network configuration capability and rely on other methods, such as embedded configuration or other customizations.

`Cloud-init` supports the following methods for disabling cloud-init.

Kernel Command Line

`Cloud-init` will additionally check for the parameter `network-config=disabled` which will automatically disable any network configuration.

Example disabling kernel command line entry:

```
network-config=disabled
```

cloud config

In the combined cloud-init configuration dictionary, merged from `/etc/cloud/cloud.cfg` and `/etc/cloud/cloud.cfg.d/*`:

```
network:
  config: disabled
```

If `Cloud-init` 's networking config has not been disabled, and no other network information is found, then it will proceed to generate a fallback networking configuration.

Disabling Network Activation

Some datasources may not be initialized until after network has been brought up. In this case, cloud-init will attempt to bring up the interfaces specified by the datasource metadata using a network activator discovered by `cloudinit.net.activators.select_activators`.

This behavior can be disabled in the cloud-init configuration dictionary, merged from `/etc/cloud/cloud.cfg` and `/etc/cloud/cloud.cfg.d/*`:

```
disable_network_activation: true
```

2.15.3 Fallback Network Configuration

`Cloud-init` will attempt to determine which of any attached network devices is most likely to have a connection and then generate a network configuration to issue a DHCP request on that interface.

`Cloud-init` runs during early boot and does not expect composed network devices (such as Bridges) to be available. `Cloud-init` does not consider the following interface devices as likely 'first' network interfaces for fallback configuration; they are filtered out from being selected.

- **loopback:** name=lo
- **Virtual Ethernet:** name=veth*
- **Software Bridges:** type=bridge
- **Software VLANs:** type=vlan

`Cloud-init` will prefer network interfaces that indicate they are connected via the Linux `carrier` flag being set. If no interfaces are marked connected, then all unfiltered interfaces are potential connections.

Of the potential interfaces, `Cloud-init` will attempt to pick the "right" interface given the information it has available.

Finally after selecting the “right” interface, a configuration is generated and applied to the system.

Note: PhotonOS disables fallback networking configuration by default leaving network unrendered when no other network config is provided. If fallback config is still desired on PhotonOS, it can be enabled by providing *disable_fallback_netcfg: false* in */etc/cloud/cloud.cfg:sys_config* settings.

2.15.4 Network Configuration Sources

Cloud-init accepts a number of different network configuration formats in support of different cloud substrates. The Datasource for these clouds in Cloud-init will detect and consume Datasource-specific network configuration formats for use when writing an instance’s network configuration.

The following Datasources optionally provide network configuration:

- *Config Drive*
 - OpenStack Metadata Service Network
 - *Network Configuration ENI (Legacy)*
- *DigitalOcean*
 - DigitalOcean JSON metadata
- *NoCloud*
 - *Networking Config Version 1*
 - *Networking Config Version 2*
 - *Network Configuration ENI (Legacy)*
- *OpenNebula*
 - *Network Configuration ENI (Legacy)*
- *OpenStack*
 - *Network Configuration ENI (Legacy)*
 - OpenStack Metadata Service Network
- *SmartOS Datasource*
 - SmartOS JSON Metadata
- *UpCloud*
 - UpCloud JSON metadata
- *Vultr*
 - Vultr JSON metadata

For more information on network configuration formats

Network Configuration ENI (Legacy)

Cloud-init supports reading and writing network config in the ENI format which is consumed by the `ifupdown` tool to parse and apply network configuration.

As an input format this is **legacy**. In cases where ENI format is available and another format is also available, it will prefer to use the other format. This can happen in either *NoCloud* or *OpenStack* datasources.

Please reference existing [documentation](#) for the `/etc/network/interfaces(5)` format.

Networking Config Version 1

This network configuration format lets users customize their instance's networking interfaces by assigning subnet configuration, virtual device creation (bonds, bridges, vlans) routes and DNS configuration.

Required elements of a Network Config Version 1 are `config` and `version`.

Cloud-init will read this format from *Base Configuration*.

For example the following could be present in `/etc/cloud/cloud.cfg.d/custom-networking.cfg`:

```
network:
  version: 1
  config:
    - type: physical
      name: eth0
      subnets:
        - type: dhcp
```

The *NoCloud* datasource can also provide cloud-init networking configuration in this Format.

Configuration Types

Within the network `config` portion, users include a list of configuration types. The current list of support `type` values are as follows:

- Physical (`physical`)
- Bond (`bond`)
- Bridge (`bridge`)
- VLAN (`vlan`)
- Nameserver (`nameserver`)
- Route (`route`)

Physical, Bond, Bridge and VLAN types may also include IP configuration under the key `subnets`.

- Subnet/IP (`subnets`)

Physical

The `physical` type configuration represents a “physical” network device, typically Ethernet-based. At least one of these entries is required for external network connectivity. Type `physical` requires only one key: `name`. A `physical` device may contain some or all of the following keys:

name: *<desired device name>*

A device's name must be less than 15 characters. Names exceeding the maximum will be truncated. This is a limitation of the Linux kernel network-device structure.

mac_address: *<MAC Address>*

The MAC Address is a device unique identifier that most Ethernet-based network devices possess. Specifying a MAC Address is optional. Letters must be lowercase.

Note: MAC addresses must be strings. As MAC addresses which consist of only the digits 0-9 (i.e. no hex a-f) can be interpreted as a base 60 integer per the [YAML 1.1 spec](#) it is best practice to quote all MAC addresses to ensure they are parsed as strings regardless of value.

Note: Cloud-init will handle the persistent mapping between a device's name and the `mac_address`.

mtu: *<MTU SizeBytes>*

The MTU key represents a device's Maximum Transmission Unit, the largest size packet or frame, specified in octets (eight-bit bytes), that can be sent in a packet- or frame-based network. Specifying `mtu` is optional.

Note: The possible supported values of a device's MTU is not available at configuration time. It's possible to specify a value too large or too small for a device and may be ignored by the device.

Physical Example:

```
network:
  version: 1
  config:
    # Simple network adapter
    - type: physical
      name: interface0
      mac_address: '00:11:22:33:44:55'
    # Second nic with Jumbo frames
    - type: physical
      name: jumbo0
      mac_address: aa:11:22:33:44:55
      mtu: 9000
    # 10G pair
    - type: physical
      name: gbe0
      mac_address: cd:11:22:33:44:00
    - type: physical
      name: gbe1
      mac_address: cd:11:22:33:44:02
```

Bond

A bond type will configure a Linux software Bond with one or more network devices. A bond type requires the following keys:

name: *<desired device name>*

A devices name must be less than 15 characters. Names exceeding the maximum will be truncated. This is a limitation of the Linux kernel network-device structure.

mac_address: *<MAC Address>*

When specifying MAC Address on a bond this value will be assigned to the bond device and may be different than the MAC address of any of the underlying bond interfaces. Specifying a MAC Address is optional. If `mac_address` is not present, then the bond will use one of the MAC Address values from one of the bond interfaces.

Note: MAC addresses must be strings. As MAC addresses which consist of only the digits 0-9 (i.e. no hex a-f) can be interpreted as a base 60 integer per the [YAML 1.1 spec](#) it is best practice to quote all MAC addresses to ensure they are parsed as strings regardless of value.

bond_interfaces: *<List of network device names>*

The `bond_interfaces` key accepts a list of network device name values from the configuration. This list may be empty.

mtu: *<MTU SizeBytes>*

The MTU key represents a device's Maximum Transmission Unit, the largest size packet or frame, specified in octets (eight-bit bytes), that can be sent in a packet- or frame-based network. Specifying `mtu` is optional.

Note: The possible supported values of a device's MTU is not available at configuration time. It's possible to specify a value too large or too small for a device and may be ignored by the device.

params: *<Dictionary of key: value bonding parameter pairs>*

The `params` key in a bond holds a dictionary of bonding parameters. This dictionary may be empty. For more details on what the various bonding parameters mean please read the `Linux Kernel Bonding.txt`.

Valid `params` keys are:

- `active_slave`: Set bond attribute
- `ad_actor_key`: Set bond attribute
- `ad_actor_sys_prio`: Set bond attribute
- `ad_actor_system`: Set bond attribute
- `ad_aggregator`: Set bond attribute
- `ad_num_ports`: Set bond attribute
- `ad_partner_key`: Set bond attribute
- `ad_partner_mac`: Set bond attribute
- `ad_select`: Set bond attribute
- `ad_user_port_key`: Set bond attribute
- `all_slaves_active`: Set bond attribute

- `arp_all_targets`: Set bond attribute
- `arp_interval`: Set bond attribute
- `arp_ip_target`: Set bond attribute
- `arp_validate`: Set bond attribute
- `downdelay`: Set bond attribute
- `fail_over_mac`: Set bond attribute
- `lacp_rate`: Set bond attribute
- `lp_interval`: Set bond attribute
- `miimon`: Set bond attribute
- `mii_status`: Set bond attribute
- `min_links`: Set bond attribute
- `mode`: Set bond attribute
- `num_grat_arp`: Set bond attribute
- `num_unsol_na`: Set bond attribute
- `packets_per_slave`: Set bond attribute
- `primary`: Set bond attribute
- `primary_reselect`: Set bond attribute
- `queue_id`: Set bond attribute
- `resend_igmp`: Set bond attribute
- `slaves`: Set bond attribute
- `tlb_dynamic_lb`: Set bond attribute
- `updelay`: Set bond attribute
- `use_carrier`: Set bond attribute
- `xmit_hash_policy`: Set bond attribute

Bond Example:

```
network:
  version: 1
  config:
    # Simple network adapter
    - type: physical
      name: interface0
      mac_address: '00:11:22:33:44:55'
    # 10G pair
    - type: physical
      name: gbe0
      mac_address: cd:11:22:33:44:00
    - type: physical
      name: gbe1
      mac_address: cd:11:22:33:44:02
    - type: bond
```

(continues on next page)

(continued from previous page)

```
name: bond0
bond_interfaces:
  - gbe0
  - gbe1
params:
  bond-mode: active-backup
```

Bridge

Type bridge requires the following keys:

- **name**: Set the name of the bridge.
- **bridge_interfaces**: Specify the ports of a bridge via their name. This list may be empty.
- **params**: A list of bridge params. For more details, please read the bridge-utils-interfaces manpage.

Valid keys are:

- **bridge_ageing**: Set the bridge's ageing value.
- **bridge_bridgeprio**: Set the bridge device network priority.
- **bridge_fd**: Set the bridge's forward delay.
- **bridge_hello**: Set the bridge's hello value.
- **bridge_hw**: Set the bridge's MAC address.
- **bridge_maxage**: Set the bridge's maxage value.
- **bridge_maxwait**: Set how long network scripts should wait for the bridge to be up.
- **bridge_pathcost**: Set the cost of a specific port on the bridge.
- **bridge_portprio**: Set the priority of a specific port on the bridge.
- **bridge_ports**: List of devices that are part of the bridge.
- **bridge_stp**: Set spanning tree protocol on or off.
- **bridge_waitport**: Set amount of time in seconds to wait on specific ports to become available.

Bridge Example:

```
network:
  version: 1
  config:
    # Simple network adapter
    - type: physical
      name: interface0
      mac_address: '00:11:22:33:44:55'
    # Second nic with Jumbo frames
    - type: physical
      name: jumbo0
      mac_address: aa:11:22:33:44:55
      mtu: 9000
    - type: bridge
      name: br0
```

(continues on next page)

(continued from previous page)

```

bridge_interfaces:
  - jumbo0
params:
  bridge_ageing: 250
  bridge_bridgeprio: 22
  bridge_fd: 1
  bridge_hello: 1
  bridge_maxage: 10
  bridge_maxwait: 0
  bridge_pathcost:
    - jumbo0 75
  bridge_pathprio:
    - jumbo0 28
  bridge_stp: 'off'
  bridge_maxwait:
    - jumbo0 0

```

VLAN

Type `vlan` requires the following keys:

- `name`: Set the name of the VLAN
- `vlan_link`: Specify the underlying link via its name.
- `vlan_id`: Specify the VLAN numeric id.

The following optional keys are supported:

mtu: *<MTU SizeBytes>*

The MTU key represents a device's Maximum Transmission Unit, the largest size packet or frame, specified in octets (eight-bit bytes), that can be sent in a packet- or frame-based network. Specifying `mtu` is optional.

Note: The possible supported values of a device's MTU is not available at configuration time. It's possible to specify a value too large or too small for a device and may be ignored by the device.

VLAN Example:

```

network:
  version: 1
  config:
    # Physical interfaces.
    - type: physical
      name: eth0
      mac_address: c0:d6:9f:2c:e8:80
    # VLAN interface.
    - type: vlan
      name: eth0.101
      vlan_link: eth0
      vlan_id: 101
      mtu: 1500

```

Nameserver

Users can specify a nameserver type. Nameserver dictionaries include the following keys:

- **address:** List of IPv4 or IPv6 address of nameservers.
- **search:** List of hostnames to include in the resolv.conf search path.
- **interface:** Optional. Ties the nameserver definition to the specified interface. The value specified here must match the *name* of an interface defined in this config. If unspecified, this nameserver will be considered a global nameserver.

Nameserver Example:

```
network:
  version: 1
  config:
    - type: physical
      name: interface0
      mac_address: '00:11:22:33:44:55'
      subnets:
        - type: static
          address: 192.168.23.14/27
          gateway: 192.168.23.1
    - type: nameserver
      interface: interface0 # Ties nameserver to interface0 only
      address:
        - 192.168.23.2
        - 8.8.8.8
      search:
        - exemplary
```

Route

Users can include static routing information as well. A route dictionary has the following keys:

- **destination:** IPv4 network address with CIDR netmask notation.
- **gateway:** IPv4 gateway address with CIDR netmask notation.
- **metric:** Integer which sets the network metric value for this route.

Route Example:

```
network:
  version: 1
  config:
    - type: physical
      name: interface0
      mac_address: '00:11:22:33:44:55'
      subnets:
        - type: static
          address: 192.168.23.14/24
          gateway: 192.168.23.1
    - type: route
      destination: 192.168.24.0/24
```

(continues on next page)

(continued from previous page)

```
gateway: 192.168.24.1
metric: 3
```

Subnet/IP

For any network device (one of the Config Types) users can define a list of `subnets` which contain ip configuration dictionaries. Multiple subnet entries will create interface alias allowing a single interface to use different ip configurations.

Valid keys for `subnets` include the following:

- `type`: Specify the subnet type.
- `control`: Specify manual, auto or hotplug. Indicates how the interface will be handled during boot.
- `address`: IPv4 or IPv6 address. It may include CIDR netmask notation.
- `netmask`: IPv4 subnet mask in dotted format or CIDR notation.
- `gateway`: IPv4 address of the default gateway for this subnet.
- `dns_nameservers`: Specify a list of IPv4 dns server IPs to end up in `resolv.conf`.
- `dns_search`: Specify a list of search paths to be included in `resolv.conf`.
- `routes`: Specify a list of routes for a given interface

Subnet types are one of the following:

- `dhcp4`: Configure this interface with IPv4 dhcp.
- `dhcp`: Alias for `dhcp4`
- `dhcp6`: Configure this interface with IPv6 dhcp.
- `static`: Configure this interface with a static IPv4.
- `static6`: Configure this interface with a static IPv6 .
- `ipv6_dhcpv6-stateful`: Configure this interface with `dhcp6`
- `ipv6_dhcpv6-stateless`: Configure this interface with SLAAC and DHCP
- `ipv6_slaac`: Configure address with SLAAC

When making use of `dhcp` or either of the `ipv6_dhcpv6` types, no additional configuration is needed in the subnet dictionary.

Using `ipv6_dhcpv6-stateless` or `ipv6_slaac` allows the IPv6 address to be automatically configured with State-Less Address AutoConfiguration ([SLAAC](#)). SLAAC requires support from the network, so verify that your cloud or network offering has support before trying it out. With `ipv6_dhcpv6-stateless`, DHCPv6 is still used to fetch other subnet details such as gateway or DNS servers. If you only want to discover the address, use `ipv6_slaac`.

Subnet DHCP Example:

```
network:
  version: 1
  config:
    - type: physical
      name: interface0
      mac_address: '00:11:22:33:44:55'
```

(continues on next page)

(continued from previous page)

```
subnets:
  - type: dhcp
```

Subnet Static Example:

```
network:
  version: 1
  config:
    - type: physical
      name: interface0
      mac_address: '00:11:22:33:44:55'
      subnets:
        - type: static
          address: 192.168.23.14/27
          gateway: 192.168.23.1
          dns_nameservers:
            - 192.168.23.2
            - 8.8.8.8
          dns_search:
            - exemplary.maas
```

The following will result in an interface0 using DHCP and interface0:1 using the static subnet configuration.

Multiple subnet Example:

```
network:
  version: 1
  config:
    - type: physical
      name: interface0
      mac_address: '00:11:22:33:44:55'
      subnets:
        - type: dhcp
        - type: static
          address: 192.168.23.14/27
          gateway: 192.168.23.1
          dns_nameservers:
            - 192.168.23.2
            - 8.8.8.8
          dns_search:
            - exemplary
```

Subnet with routes Example:

```
network:
  version: 1
  config:
    - type: physical
      name: interface0
      mac_address: '00:11:22:33:44:55'
      subnets:
        - type: dhcp
        - type: static
```

(continues on next page)

(continued from previous page)

```

address: 10.184.225.122
netmask: 255.255.255.252
routes:
  - gateway: 10.184.225.121
    netmask: 255.240.0.0
    network: 10.176.0.0
  - gateway: 10.184.225.121
    netmask: 255.240.0.0
    network: 10.208.0.0

```

Multi-layered configurations

Complex networking sometimes uses layers of configuration. The syntax allows users to build those layers one at a time. All of the virtual network devices supported allow specifying an underlying device by their name value.

Bonded VLAN Example:

```

network:
  version: 1
  config:
    # 10G pair
    - type: physical
      name: gbe0
      mac_address: cd:11:22:33:44:00
    - type: physical
      name: gbe1
      mac_address: cd:11:22:33:44:02
    # Bond.
    - type: bond
      name: bond0
      bond_interfaces:
        - gbe0
        - gbe1
      params:
        bond-mode: 802.3ad
        bond-lacp-rate: fast
    # A Bond VLAN.
    - type: vlan
      name: bond0.200
      vlan_link: bond0
      vlan_id: 200
      subnets:
        - type: dhcp4

```

More Examples

Some more examples to explore the various options available.

Multiple VLAN example:

```
network:
  version: 1
  config:
    - id: eth0
      mac_address: d4:be:d9:a8:49:13
      mtu: 1500
      name: eth0
      subnets:
        - address: 10.245.168.16/21
          dns_nameservers:
            - 10.245.168.2
          gateway: 10.245.168.1
          type: static
      type: physical
    - id: eth1
      mac_address: d4:be:d9:a8:49:15
      mtu: 1500
      name: eth1
      subnets:
        - address: 10.245.188.2/24
          dns_nameservers: []
          type: static
      type: physical
    - id: eth1.2667
      mtu: 1500
      name: eth1.2667
      subnets:
        - address: 10.245.184.2/24
          dns_nameservers: []
          type: static
      type: vlan
      vlan_id: 2667
      vlan_link: eth1
    - id: eth1.2668
      mtu: 1500
      name: eth1.2668
      subnets:
        - address: 10.245.185.1/24
          dns_nameservers: []
          type: static
      type: vlan
      vlan_id: 2668
      vlan_link: eth1
    - id: eth1.2669
      mtu: 1500
      name: eth1.2669
      subnets:
```

(continues on next page)

(continued from previous page)

```

- address: 10.245.186.1/24
  dns_nameservers: []
  type: static
type: vlan
vlan_id: 2669
vlan_link: eth1
- id: eth1.2670
  mtu: 1500
  name: eth1.2670
  subnets:
  - address: 10.245.187.2/24
    dns_nameservers: []
    type: static
  type: vlan
  vlan_id: 2670
  vlan_link: eth1
- address: 10.245.168.2
  search:
  - dellstack
  type: nameserver

```

Networking Config Version 2

Cloud-init's support for Version 2 network config is a subset of the version 2 format defined for the [netplan](#) tool. Cloud-init supports both reading and writing of Version 2; the latter support requires a distro with [netplan](#) present.

Netplan Passthrough

On a system with netplan present, cloud-init will pass Version 2 configuration through to netplan without modification. On such systems, you do not need to limit yourself to the below subset of netplan's configuration format.

Warning: If you are writing or generating network configuration that may be used on non-netplan systems, you **must** limit yourself to the subset described in this document, or you will see network configuration failures on non-netplan systems.

Version 2 Configuration Format

The `network` key has at least two required elements. First it must include `version: 2` and one or more of possible device types.

Cloud-init will read this format from *Base Configuration*.

For example the following could be present in `/etc/cloud/cloud.cfg.d/custom-networking.cfg`:

```

network:
  version: 2
  ethernets: []

```

It may also be provided in other locations including the *NoCloud*, see *Default Behavior* for other places.

Supported device types values are as follows:

- Ethernets (ethernets)
- Bonds (bonds)
- Bridges (bridges)
- VLANs (vlans)

Each type block contains device definitions as a map where the keys (called “configuration IDs”). Each entry under the types may include IP and/or device configuration.

Device configuration IDs

The key names below the per-device-type definition maps (like `ethernets:`) are called “ID”s. They must be unique throughout the entire set of configuration files. Their primary purpose is to serve as anchor names for composite devices, for example to enumerate the members of a bridge that is currently being defined.

There are two physically/structurally different classes of device definitions, and the ID field has a different interpretation for each:

Physical devices (Examples: ethernet, wifi):

These can dynamically come and go between reboots and even during runtime (hotplugging). In the generic case, they can be selected by `match:` rules on desired properties, such as name/name pattern, MAC address, driver, or device paths. In general these will match any number of devices (unless they refer to properties which are unique such as the full path or MAC address), so without further knowledge about the hardware these will always be considered as a group.

It is valid to specify no match rules at all, in which case the ID field is simply the interface name to be matched. This is mostly useful if you want to keep simple cases simple, and it’s how network device configuration has been done for a long time.

If there are `match:` rules, then the ID field is a purely opaque name which is only being used for references from definitions of compound devices in the config.

Virtual devices (Examples: veth, bridge, bond):

These are fully under the control of the config file(s) and the network stack. I. e. these devices are being created instead of matched. Thus `match:` and `set-name:` are not applicable for these, and the ID field is the name of the created virtual device.

Common properties for physical device types

match: *<(mapping)>*

This selects a subset of available physical devices by various hardware properties. The following configuration will then apply to all matching devices, as soon as they appear. *All* specified properties must match. The following properties for creating matches are supported:

name: *<(scalar)>*

Current interface name. Globs are supported, and the primary use case for matching on names, as selecting one fixed name can be more easily achieved with having no `match:` at all and just using the ID (see above). Note that currently only networkd supports globbing, NetworkManager does not.

macaddress: *<(scalar)>*

Device’s MAC address in the form `xx:xx:xx:xx:xx:xx`. Globs are not allowed. Letters must be lowercase.

Note: MAC addresses must be strings. As MAC addresses which consist of only the digits 0-9 (i.e. no hex a-f) can be interpreted as a base 60 integer per the [YAML 1.1 spec](#) it is best practice to quote all MAC addresses to ensure they are parsed as strings regardless of value.

driver: *<(scalar)>*

Kernel driver name, corresponding to the DRIVER udev property. Globs are supported. Matching on driver is *only* supported with networkd.

Examples:

```
# all cards on second PCI bus
match:
  name: enp2*

# fixed MAC address
match:
  macaddress: 11:22:33:aa:bb:ff

# first card of driver `ixgbe`
match:
  driver: ixgbe
  name: en*s0
```

set-name: *<(scalar)>*

When matching on unique properties such as path or MAC, or with additional assumptions such as “there will only ever be one wifi device”, match rules can be written so that they only match one device. Then this property can be used to give that device a more specific/desirable/nicer name than the default from udev’s ifnames. Any additional device that satisfies the match rules will then fail to get renamed and keep the original kernel name (and dmesg will show an error).

wakeonlan: *<(bool)>*

Enable wake on LAN. Off by default.

Common properties for all device types

renderer: *<(scalar)>*

Use the given networking backend for this definition. Currently supported are **networkd** and **NetworkManager**. This property can be specified globally in **networks:**, for a device type (in e. g. **ethernets:**) or for a particular device definition. Default is **networkd**.

Note: Cloud-init only supports networkd backend if rendering version2 config to the instance.

dhcp4: *<(bool)>*

Enable DHCP for IPv4. Off by default.

dhcp6: *<(bool)>*

Enable DHCP for IPv6. Off by default.

dhcp4-overrides and **dhcp6-overrides:** *<(mapping)>*

DHCP behavior overrides. Overrides will only have an effect if the corresponding DHCP type is enabled. Refer to [netplan#dhcp-overrides](#) for more documentation.

Note: These properties are only consumed on netplan and networkd renderers.

The netplan renderer *passes through* everything and the networkd renderer consumes the following sub-properties:

- hostname *
- route-metric *
- send-hostname *
- use-dns
- use-domains
- use-hostname
- use-mtu *
- use-ntp
- use-routes *

Note: Sub-properties marked with a * are unsupported for dhcp6-overrides when used with the networkd renderer.

Example:

```
dhcp4-overrides:
  hostname: hal
  route-metric: 1100
  send-hostname: false
  use-dns: false
  use-domains: false
  use-hostname: false
  use-mtu: false
  use-ntp: false
  use-routes: false
```

addresses: *<(sequence of scalars)>*

Add static addresses to the interface in addition to the ones received through DHCP or RA. Each sequence entry is in CIDR notation, i. e. of the form `addr/prefixlen`. `addr` is an IPv4 or IPv6 address as recognized by `inet_pton(3)` and `prefixlen` the number of bits of the subnet.

Example: `addresses: [192.168.14.2/24, 2001:1::1/64]`

gateway4: or **gateway6:** *<(scalar)>*

Set default gateway for IPv4/6, for manual address configuration. This requires setting addresses too. Gateway IPs must be in a form recognized by `inet_pton(3)`

Example for IPv4: `gateway4: 172.16.0.1` Example for IPv6: `gateway6: 2001:4::1`

mtu: *<MTU SizeBytes>*

The MTU key represents a device's Maximum Transmission Unit, the largest size packet or frame, specified in octets (eight-bit bytes), that can be sent in a packet- or frame-based network. Specifying `mtu` is optional.

nameservers: *<(mapping)>*

Set DNS servers and search domains, for manual address configuration. There are two supported fields: `addresses:` is a list of IPv4 or IPv6 addresses similar to `gateway*`, and `search:` is a list of search domains.

Example:

```
nameservers:
  search: [lab, home]
  addresses: [8.8.8.8, FEDC::1]
```

routes: *<(sequence of mapping)>*

Add device specific routes. Each mapping includes a `to`, `via` key with an IPv4 or IPv6 address as value. `metric` is an optional value.

Example:

```
routes:
- to: 0.0.0.0/0
  via: 10.23.2.1
  metric: 3
```

Ethernets

Ethernet device definitions do not support any specific properties beyond the common ones described above.

Bonds

interfaces *<(sequence of scalars)>*

All devices matching this ID list will be added to the bond.

Example:

```
ethernets:
  switchports:
    match: {name: "enp2*"}
[... ]
bonds:
  bond0:
    interfaces: [switchports]
```

parameters: *<(mapping)>*

Customization parameters for special bonding options. Time values are specified in seconds unless otherwise specified.

mode: *<(scalar)>*

Set the bonding mode used for the interfaces. The default is `balance-rr` (round robin). Possible values are `balance-rr`, `active-backup`, `balance-xor`, `broadcast`, `802.3ad`, `balance-tlb`, and `balance-alb`.

lacp-rate: *<(scalar)>*

Set the rate at which LACPDU's are transmitted. This is only useful in 802.3ad mode. Possible values are `slow` (30 seconds, default), and `fast` (every second).

mii-monitor-interval: *<(scalar)>*

Specifies the interval for MII monitoring (verifying if an interface of the bond has carrier). The default is `0`; which disables MII monitoring.

min-links: *<(scalar)>*

The minimum number of links up in a bond to consider the bond interface to be up.

transmit-hash-policy: *<(scalar)>*

Specifies the transmit hash policy for the selection of slaves. This is only useful in `balance-xor`, `802.3ad` and `balance-tlb` modes. Possible values are `layer2`, `layer3+4`, `layer2+3`, `encap2+3`, and `encap3+4`.

ad-select: *<(scalar)>*

Set the aggregation selection mode. Possible values are `stable`, `bandwidth`, and `count`. This option is only used in `802.3ad` mode.

all-slaves-active: *<(bool)>*

If the bond should drop duplicate frames received on inactive ports, set this option to `false`. If they should be delivered, set this option to `true`. The default value is `false`, and is the desirable behavior in most situations.

arp-interval: *<(scalar)>*

Set the interval value for how frequently ARP link monitoring should happen. The default value is `0`, which disables ARP monitoring.

arp-ip-targets: *<(sequence of scalars)>*

IPs of other hosts on the link which should be sent ARP requests in order to validate that a slave is up. This option is only used when `arp-interval` is set to a value other than `0`. At least one IP address must be given for ARP link monitoring to function. Only IPv4 addresses are supported. You can specify up to 16 IP addresses. The default value is an empty list.

arp-validate: *<(scalar)>*

Configure how ARP replies are to be validated when using ARP link monitoring. Possible values are `none`, `active`, `backup`, and `all`.

arp-all-targets: *<(scalar)>*

Specify whether to use any ARP IP target being up as sufficient for a slave to be considered up; or if all the targets must be up. This is only used for `active-backup` mode when `arp-validate` is enabled. Possible values are `any` and `all`.

up-delay: *<(scalar)>*

Specify the delay before enabling a link once the link is physically up. The default value is `0`.

down-delay: *<(scalar)>*

Specify the delay before disabling a link once the link has been lost. The default value is `0`.

fail-over-mac-policy: *<(scalar)>*

Set whether to set all slaves to the same MAC address when adding them to the bond, or how else the system should handle MAC addresses. The possible values are `none`, `active`, and `follow`.

gratuitous-arp: *<(scalar)>*

Specify how many ARP packets to send after failover. Once a link is up on a new slave, a notification is sent and possibly repeated if this value is set to a number greater than 1. The default value is 1 and valid values are between 1 and 255. This only affects `active-backup` mode.

packets-per-slave: *<(scalar)>*

In `balance-rr` mode, specifies the number of packets to transmit on a slave before switching to the next. When this value is set to `0`, slaves are chosen at random. Allowable values are between `0` and `65535`. The default value is `1`. This setting is only used in `balance-rr` mode.

primary-reselect-policy: *<(scalar)>*

Set the reselection policy for the primary slave. On failure of the active slave, the system will use this policy to decide how the new active slave will be chosen and how recovery will be handled. The possible values are `always`, `better`, and `failure`.

learn-packet-interval: *<(scalar)>*

Specify the interval between sending learning packets to each slave. The value range is between `1` and `0xffffffff`. The default value is `1`. This option only affects `balance-tlb` and `balance-alb` modes.

Bridges

interfaces: *<(sequence of scalars)>*

All devices matching this ID list will be added to the bridge.

Example:

```
ethernets:
  switchports:
    match: {name: "enp2*"}
  [...]
bridges:
  br0:
    interfaces: [switchports]
```

parameters: *<(mapping)>*

Customization parameters for special bridging options. Time values are specified in seconds unless otherwise specified.

ageing-time: *<(scalar)>*

Set the period of time to keep a MAC address in the forwarding database after a packet is received.

priority: *<(scalar)>*

Set the priority value for the bridge. This value should be an number between `0` and `65535`. Lower values mean higher priority. The bridge with the higher priority will be elected as the root bridge.

forward-delay: *<(scalar)>*

Specify the period of time the bridge will remain in Listening and Learning states before getting to the Forwarding state. This value should be set in seconds for the systemd backend, and in milliseconds for the NetworkManager backend.

hello-time: *<(scalar)>*

Specify the interval between two hello packets being sent out from the root and designated bridges. Hello packets communicate information about the network topology.

max-age: *<(scalar)>*

Set the maximum age of a hello packet. If the last hello packet is older than that value, the bridge will attempt to become the root bridge.

path-cost: *<(scalar)>*

Set the cost of a path on the bridge. Faster interfaces should have a lower cost. This allows a finer control on the network topology so that the fastest paths are available whenever possible.

stp: *<(bool)>*

Define whether the bridge should use Spanning Tree Protocol. The default value is “true”, which means that Spanning Tree should be used.

VLANs

id: *<(scalar)>*

VLAN ID, a number between 0 and 4094.

link: *<(scalar)>*

ID of the underlying device definition on which this VLAN gets created.

Example:

```
ethernets:
  eno1: {...}
vlangs:
  en-intra:
    id: 1
    link: eno1
    dhcp4: yes
  en-vpn:
    id: 2
    link: eno1
    address: ...
```

Examples

Configure an ethernet device with networkd, identified by its name, and enable DHCP:

```
network:
  version: 2
  ethernets:
    eno1:
      dhcp4: true
```

This is a complex example which shows most available features:

```
network:
  version: 2
  ethernets:
    # opaque ID for physical interfaces, only referred to by other stanzas
    id0:
      match:
        macaddress: '00:11:22:33:44:55'
      wakeonlan: true
      dhcp4: true
      addresses:
        - 192.168.14.2/24
        - 2001:1::1/64
      gateway4: 192.168.14.1
```

(continues on next page)

(continued from previous page)

```

gateway6: 2001:1::2
nameservers:
  search: [foo.local, bar.local]
  addresses: [8.8.8.8]
# static routes
routes:
  - to: 192.0.2.0/24
    via: 11.0.0.1
    metric: 3
lom:
  match:
    driver: ixgbe
    # you are responsible for setting tight enough match rules
    # that only match one device if you use set-name
  set-name: lom1
  dhcp6: true
switchports:
  # all cards on second PCI bus; unconfigured by themselves, will be added
  # to br0 below
  match:
    name: enp2*
  mtu: 1280
bonds:
  bond0:
    interfaces: [id0, lom]
bridges:
  # the key name is the name for virtual (created) interfaces; no match: and
  # set-name: allowed
  br0:
    # IDs of the components; switchports expands into multiple interfaces
    interfaces: [wlp1s0, switchports]
    dhcp4: true
vlans:
  en-intra:
    id: 1
    link: id0
    dhcp4: yes

```

2.15.5 Network Configuration Outputs

Cloud-init converts various forms of user supplied or automatically generated configuration into an internal network configuration state. From this state Cloud-init delegates rendering of the configuration to Distro supported formats. The following renderers are supported in cloud-init:

- **NetworkManager**

NetworkManager is the standard Linux network configuration tool suite. It supports a wide range of networking setups. Configuration is typically stored in `/etc/NetworkManager`.

It is the default for a number of Linux distributions, notably Fedora; CentOS/RHEL; and derivatives.

- **ENI**

`/etc/network/interfaces` or ENI is supported by the `ifupdown` package found in Alpine Linux, Debian and Ubuntu.

- **Netplan**

Introduced in Ubuntu 16.10 (Yakkety Yak), [netplan](#) has been the default network configuration tool in Ubuntu since 17.10 (Artful Aardvark). [netplan](#) consumes [Networking Config Version 2](#) input and renders network configuration for supported backends such as [systemd-networkd](#) and [NetworkManager](#).

- **Sysconfig**

Sysconfig format is used by RHEL, CentOS, Fedora and other derivatives.

- **NetBSD, OpenBSD, FreeBSD**

Network renders supporting BSD releases which typically write configuration to `/etc/rc.conf`. Unique to BSD renderers is that each renderer also calls something akin to [FreeBSD.start_services](#) which will invoke applicable network services to setup the network, making network activators unneeded for BSD flavors at the moment.

2.15.6 Network Output Policy

The default policy for selecting a network `renderer` in order of preference is as follows:

- ENI
- Sysconfig
- Netplan
- NetworkManager
- FreeBSD
- NetBSD
- OpenBSD
- Networkd

The default policy for selecting a network `activator` in order of preference is as follows: - ENI: using *ifup*, *ifdown* to manage device setup/teardown - Netplan: using *netplan apply* to manage device setup/teardown - NetworkManager: using *nmcli* to manage device setup/teardown - Networkd: using *ip* to manage device setup/teardown

When applying the policy, [Cloud-init](#) checks if the current instance has the correct binaries and paths to support the `renderer`. The first `renderer` that can be used is selected. Users may override the network `renderer` policy by supplying an updated configuration in `cloud-config`.

```
system_info:
  network:
    renderers: ['netplan', 'network-manager', 'eni', 'sysconfig', 'freebsd', 'netbsd',
↪ 'openbsd']
    activators: ['eni', 'netplan', 'network-manager', 'networkd']
```

2.15.7 Network Configuration Tools

Cloud-init contains one tool used to test input/output conversion between formats. The `tools/net-convert.py` in the Cloud-init source repository is helpful for examining expected output for a given input format.

CLI Interface :

```
% tools/net-convert.py --help
usage: net-convert.py [-h] --network-data PATH --kind
                    {eni,network_data.json,yaml} -d PATH [-m name,mac]
                    --output-kind {eni,netplan,sysconfig}

optional arguments:
  -h, --help            show this help message and exit
  --network-data PATH, -p PATH
                        directory to place output in
  --kind {eni,network_data.json,yaml}, -k {eni,network_data.json,yaml}
                        interface name to mac mapping
  -d PATH, --directory PATH
                        directory to place output in
  -m name,mac, --mac name,mac
                        interface name to mac mapping
  --output-kind {eni,netplan,sysconfig}, -ok {eni,netplan,sysconfig}
```

Example output converting V2 to sysconfig:

```
% tools/net-convert.py --network-data v2.yaml --kind yaml \
  --output-kind sysconfig -d target
% cat target/etc/sysconfig/network-scripts/ifcfg-eth*
# Created by cloud-init on instance boot automatically, do not edit.
#
BOOTPROTO=static
DEVICE=eth7
IPADDR=192.168.1.5/255.255.255.0
NM_CONTROLLED=no
ONBOOT=yes
TYPE=Ethernet
USERCTL=no
# Created by cloud-init on instance boot automatically, do not edit.
#
BOOTPROTO=dhcp
DEVICE=eth9
NM_CONTROLLED=no
ONBOOT=yes
TYPE=Ethernet
USERCTL=no
```

2.16 Base Configuration

Warning: This documentation is intended for custom image creators, such as distros and cloud providers, not end users. Modifying the base configuration should not be necessary for end users and can result in a system that may be unreachable or may no longer boot.

Cloud-init base config is primarily defined in two places:

- `/etc/cloud/cloud.cfg`
- `/etc/cloud/cloud.cfg.d/*.cfg`

See the [configuration sources explanation](#) for more information on how these files get sourced and combined with other configuration.

2.16.1 Generation

`cloud.cfg` isn't present in any of cloud-init's source files. The configuration is templated and customized for each distribution supported by cloud-init.

2.16.2 Base Configuration Keys

Module Keys

Modules are grouped into the following keys:

- **cloud_init_modules:** Modules run during *network* timeframe.
- **cloud_config_modules:** Modules run during *config* timeframe.
- **cloud_final_modules:** Modules run during *final* timeframe.

Each modules definition contains an array of strings, where each string is the name of the module. Each name is taken directly from the module filename, with the `cc_` prefix and `.py` suffix removed, and with `-` and `_` being interchangeable.

Alternatively, in place of the module name, an array of `<name>`, `<frequency>`[, `<args>`] args may be specified. See [the module creation guidelines](#) for more information on frequency and args.

Note: Most modules won't run at all if they're not triggered via a respective user data key, so removing modules or changing the run frequency is **not** a recommended way to reduce instance boot time.

Examples

To specify that only `cc_final_message.py` run during final timeframe:

```
cloud_final_modules:  
- final_message
```

To change the frequency from the default of ALWAYS to ONCE:

```
cloud_final_modules:
- [final_message, once]
```

To include default arguments to the module (that may be overridden by user data):

```
cloud_final_modules:
- [final_message, once, "my final message"]
```

Datasource Keys

Many datasources allow configuration of the datasource for use in querying the datasource for metadata using the `datasource` key. This configuration is datasource dependent and can be found under each datasource's respective *documentation*. It will generally take the form of:

```
datasource:
  <datasource_name>:
    ...
```

System Info Keys

These keys are used for setup of cloud-init itself, or the datasource or distro. Anything under the `system_info` cannot be overridden by vendor data, user data, or any other handlers or transforms. In some cases, there may be a `system_info` key used for the distro, while the same key is used outside of `system_info` for a userdata module. Both keys will be processed independently.

- **system_info**: Top-level key
 - **paths**: Definitions of common paths used by cloud-init
 - * **cloud_dir**: Defaults to `/var/lib/cloud`
 - * **templates_dir**: Defaults to `/etc/cloud/templates`
 - **distro**: Name of distro being used.
 - **default_user**: Defines the default user for the system using the same user configuration as *Users and Groups*. Note that this CAN be overridden if a `users` configuration is specified without a `- default` entry.
 - **ntp_client**: The default ntp client for the distro. Takes the same form as `ntp_client` defined in *NTP*.
 - **package_mirrors**: Defines the package mirror info for apt.
 - **ssh_svcname**: The ssh service name. For most distros this will be either `ssh` or `sshd`.
 - **network**: Top-level key for distro-specific networking configuration
 - * **renderers**: Prioritized list of networking configurations to try on this system. The first valid entry found will be used. Options are:
 - **eni** - For `/etc/network/interfaces`
 - **network-manager**
 - **netplan**
 - **networkd** - For `systemd-networkd`
 - **freebsd**

- **netbsd**
- **openbsd**
- * **activators**: Prioritized list of networking tools to try to activate network on this system. The first valid entry found will be used. Options are:
 - **eni** - For ifup/ifdown
 - **netplan** - For netplan generate/netplan apply
 - **network-manager** - For nmcli connection load/nmcli connection up
 - **networkd** - For ip link set up/ip link set down

Logging Keys

See *the logging explanation* for a comprehensive logging explanation. Note that cloud-init has a default logging definition that shouldn't need to be altered. It is defined on the instance at `/etc/cloud/cloud.cfg.d/05_logging.cfg`.

The logging keys used in the base configuration are as follows:

logcfg: A standard python `fileConfig` formatted log configuration. This is the primary logging configuration key and will take precedence over **log_cfgs** or **log_basic** keys.

log_cfgs: A list of logging configs in `fileConfig` format to apply when running cloud-init. Note that **log_cfgs** is used in `/etc/cloud/cloud.cfg.d/05_logging.cfg`.

log_basic: Boolean value to determine if cloud-init should apply a basic default logging configuration if none has been provided. Defaults to `true` but only takes effect if **logcfg** or **log_cfgs** hasn't been defined.

output: If and how to redirect stdout/stderr. Defined in `/etc/cloud/cloud.cfg.d/05_logging.cfg` and explained in *the logging explanation*.

syslog_fix_perms: Takes a list of `<owner:group>` strings and will set the owner of **def_log_file** accordingly.

def_log_file: Only used in conjunction with **syslog_fix_perms**. Specifies the filename to be used for setting permissions. Defaults to `/var/log/cloud-init.log`.

Other Keys

network: The *Network Configuration* to be applied to this instance.

datasource_pkg_list: Prioritized list of python packages to search when finding a datasource. Automatically includes `cloudinit.sources`.

datasource_list: Prioritized list of datasources that cloud-init will attempt to find on boot. By default, this will be defined in `/etc/cloud/cloud.cfg.d`. There are two primary use cases for modifying the `datasource_list`:

1. Remove known invalid datasources. This may avoid long timeouts attempting to detect datasources on any system without a `systemd-generator` hook that invokes `ds-identify`.
2. Override default datasource ordering to discover a different datasource type than would typically be prioritized.

If **datasource_list** has only a single entry (or a single entry + `None`), *cloud-init's generator script* will automatically assume and use this datasource without attempting detection.

vendor_data/vendor_data2: Allows the user to disable `vendor_data` or `vendor_data2` along with providing a prefix for any executed scripts.

Format is a dict with `enabled` and `prefix` keys:

- **enabled**: Boolean indicating whether to enable or disable the `vendor_data`

- **prefix:** A path to prepend to any vendor_data provided script

2.16.3 Example

On an ubuntu system, /etc/cloud/cloud.cfg should look similar to:

```
# The top level settings are used as module and base configuration.
# A set of users which may be applied and/or used by various modules
# when a 'default' entry is found it will reference the 'default_user'
# from the distro configuration specified below
users:
- default

# If this is set, 'root' will not be able to ssh in and they
# will get a message to login instead as the default $user
disable_root: true

# This will cause the set+update hostname module to not operate (if true)
preserve_hostname: false

# If you use datasource_list array, keep array items in a single line.
# If you use multi line array, ds-identify script won't read array items.
# Example datasource config
# datasource:
#   Ec2:
#     metadata_urls: [ 'blah.com' ]
#     timeout: 5 # (defaults to 50 seconds)
#     max_wait: 10 # (defaults to 120 seconds)

# The modules that run in the 'init' stage
cloud_init_modules:
- migrator
- seed_random
- bootcmd
- write-files
- growpart
- resizefs
- disk_setup
- mounts
- set_hostname
- update_hostname
- update_etc_hosts
- ca-certs
- rsyslog
- users-groups
- ssh

# The modules that run in the 'config' stage
cloud_config_modules:
- snap
- ssh-import-id
- keyboard
```

(continues on next page)

(continued from previous page)

```

- locale
- set-passwords
- grub-dpkg
- apt-pipelining
- apt-configure
- ubuntu-advantage
- ntp
- timezone
- disable-ec2-metadata
- runcmd
- byobu

# The modules that run in the 'final' stage
cloud_final_modules:
- package-update-upgrade-install
- fan
- landscape
- lxd
- ubuntu-drivers
- write-files-deferred
- puppet
- chef
- mcollective
- salt-minion
- reset_rmc
- refresh_rmc_and_interface
- rightscale_userdata
- scripts-vendor
- scripts-per-once
- scripts-per-boot
- scripts-per-instance
- scripts-user
- ssh-authkey-fingerprints
- keys-to-console
- install-hotplug
- phone-home
- final-message
- power-state-change

# System and/or distro specific settings
# (not accessible to handlers/transforms)
system_info:
  # This will affect which distro class gets used
  distro: ubuntu
  # Default user name + that default users groups (if added/used)
  default_user:
    name: ubuntu
    lock_passwd: True
    gecol: Ubuntu
    groups: [adm, audio, cdrom, dialout, dip, floppy, lxd, netdev, plugdev, sudo, video]
    sudo: ["ALL=(ALL) NOPASSWD:ALL"]
    shell: /bin/bash

```

(continues on next page)

(continued from previous page)

```

network:
  renderers: ['netplan', 'eni', 'sysconfig']
  # Automatically discover the best ntp_client
ntp_client: auto
  # Other config here will be given to the distro class and/or path classes
paths:
  cloud_dir: /var/lib/cloud/
  templates_dir: /etc/cloud/templates/
package_mirrors:
  - arches: [i386, amd64]
failsafe:
  primary: http://archive.ubuntu.com/ubuntu
  security: http://security.ubuntu.com/ubuntu
search:
  primary:
    - http://%(ec2_region)s.ec2.archive.ubuntu.com/ubuntu/
    - http://%(availability_zone)s.clouds.archive.ubuntu.com/ubuntu/
    - http://%(region)s.clouds.archive.ubuntu.com/ubuntu/
  security: []
  - arches: [arm64, armel, armhf]
failsafe:
  primary: http://ports.ubuntu.com/ubuntu-ports
  security: http://ports.ubuntu.com/ubuntu-ports
search:
  primary:
    - http://%(ec2_region)s.ec2.ports.ubuntu.com/ubuntu-ports/
    - http://%(availability_zone)s.clouds.ports.ubuntu.com/ubuntu-ports/
    - http://%(region)s.clouds.ports.ubuntu.com/ubuntu-ports/
  security: []
  - arches: [default]
failsafe:
  primary: http://ports.ubuntu.com/ubuntu-ports
  security: http://ports.ubuntu.com/ubuntu-ports
ssh_svcname: ssh

```

2.17 Module Reference

2.17.1 Ansible

Summary: Configure ansible for instance

This module provides ansible integration for augmenting cloud-init's configuration of the local node.

This module installs ansible during boot and then uses `ansible-pull` to run the playbook repository at the remote URL.

Internal name: `cc_ansible`

Module frequency: once-per-instance

Supported distros: all

Activate only on keys: `ansible`

Config schema:**ansible:** (object)**install_method:** (distro/pip) The type of installation for ansible. It can be one of the following values:

- distro
- pip.

run_user: (string) User to run module commands as. If install_method: pip, the pip install runs as this user as well.**ansible_config:** (string) Sets the ANSIBLE_CONFIG environment variable. If set, overrides default config.**setup_controller:** (object)**repositories:** (array of object)Each object in **repositories** list supports the following keys:**path:** (string)**source:** (string)**run_ansible:** (array)Each object in **run_ansible** list supports the following keys:**playbook_name:** (string)**playbook_dir:** (string)**become_password_file:** (string)**connection_password_file:** (string)**list_hosts:** (boolean)**syntax_check:** (boolean)**timeout:** (number)**vault_id:** (string)**vault_password_file:** (string)**background:** (number)**check:** (boolean)**diff:** (boolean)**module_path:** (string)**poll:** (number)**args:** (string)**extra_vars:** (string)**forks:** (number)**inventory:** (string)**scp_extra_args:** (string)**sftp_extra_args:** (string)

private_key: (string)
connection: (string)
module_name: (string)
sleep: (string)
tags: (string)
skip_tags: (string)
galaxy: (object)
 actions: (array of array)
package_name: (string)
pull: (object)
 accept_host_key: (boolean)
 clean: (boolean)
 full: (boolean)
 diff: (boolean)
 ssh_common_args: (string)
 scp_extra_args: (string)
 sftp_extra_args: (string)
 private_key: (string)
 checkout: (string)
 module_path: (string)
 timeout: (string)
 url: (string)
 connection: (string)
 vault_id: (string)
 vault_password_file: (string)
 module_name: (string)
 sleep: (string)
 tags: (string)
 skip_tags: (string)
 playbook_name: (string)

Examples:

```

ansible:
  install_method: distro
  pull:
    url: "https://github.com/holmanb/vmboot.git"
    playbook_name: ubuntu.yml
  
```

(continues on next page)

(continued from previous page)

```
# --- Example2 ---
ansible:
  package_name: ansible-core
  install_method: pip
  pull:
    url: "https://github.com/holmanb/vmboot.git"
    playbook_name: ubuntu.yml
```

2.17.2 APK Configure

Summary: Configure apk repositories file

This module handles configuration of the `/etc/apk/repositories` file.

Note: To ensure that apk configuration is valid yaml, any strings containing special characters, especially `:` should be quoted.

Internal name: `cc_apk_configure`

Module frequency: once-per-instance

Supported distros: alpine

Activate only on keys: `apk_repos`

Config schema:

apk_repos: (object)

preserve_repositories: (boolean) By default, cloud-init will generate a new repositories file `/etc/apk/repositories` based on any valid configuration settings specified within a `apk_repos` section of cloud config. To disable this behavior and preserve the repositories file from the pristine image, set `preserve_repositories` to `true`.

The `preserve_repositories` option overrides all other config keys that would alter `/etc/apk/repositories`.

alpine_repo: (null/object)

base_url: (string) The base URL of an Alpine repository, or mirror, to download official packages from. If not specified then it defaults to `https://alpine.global.ssl.fastly.net/alpine`.

community_enabled: (boolean) Whether to add the Community repo to the repositories file. By default the Community repo is not included.

testing_enabled: (boolean) Whether to add the Testing repo to the repositories file. By default the Testing repo is not included. It is only recommended to use the Testing repo on a machine running the Edge version of Alpine as packages installed from Testing may have dependencies that conflict with those in non-Edge Main or Community repos.

version: (string) The Alpine version to use (e.g. `v3.12` or `edge`).

local_repo_base_url: (string) The base URL of an Alpine repository containing unofficial packages.

Examples:

```
# Keep the existing /etc/apk/repositories file unaltered.
apk_repos:
  preserve_repositories: true

# --- Example2 ---
# Create repositories file for Alpine v3.12 main and community
# using default mirror site.
apk_repos:
  alpine_repo:
    community_enabled: true
    version: 'v3.12'

# --- Example3 ---
# Create repositories file for Alpine Edge main, community, and
# testing using a specified mirror site and also a local repo.
apk_repos:
  alpine_repo:
    base_url: 'https://some-alpine-mirror/alpine'
    community_enabled: true
    testing_enabled: true
    version: 'edge'
  local_repo_base_url: 'https://my-local-server/local-alpine'
```

2.17.3 Apt Configure

Summary: Configure apt for the user

This module handles both configuration of apt options and adding source lists. There are configuration options such as `apt_get_wrapper` and `apt_get_command` that control how cloud-init invokes apt-get. These configuration options are handled on a per-distro basis, so consult documentation for cloud-init's distro support for instructions on using these config options.

Note: To ensure that apt configuration is valid yaml, any strings containing special characters, especially `:` should be quoted.

Note: For more information about apt configuration, see the `Additional apt configuration example`.

Internal name: `cc_apt_configure`

Module frequency: once-per-instance

Supported distros: ubuntu, debian

Config schema:

apt: (object)

preserve_sources_list: (boolean) By default, cloud-init will generate a new sources list in `/etc/apt/sources.list.d` based on any changes specified in cloud config. To disable this behavior and preserve the sources list from the pristine image, set `preserve_sources_list` to `true`.

The `preserve_sources_list` option overrides all other config keys that would alter `sources.list` or `sources.list.d`, **except** for additional sources to be added to `sources.list.d`.

disable_suites: (array of string) Entries in the sources list can be disabled using `disable_suites`, which takes a list of suites to be disabled. If the string `$RELEASE` is present in a suite in the `disable_suites` list, it will be replaced with the release name. If a suite specified in `disable_suites` is not present in `sources.list` it will be ignored. For convenience, several aliases are provided for `disable_suites`:

- `updates => $RELEASE-updates`
- `backports => $RELEASE-backports`
- `security => $RELEASE-security`
- `proposed => $RELEASE-proposed`
- `release => $RELEASE.`

When a suite is disabled using `disable_suites`, its entry in `sources.list` is not deleted; it is just commented out.

primary: (array of object) The primary and security archive mirrors can be specified using the `primary` and `security` keys, respectively. Both the `primary` and `security` keys take a list of configs, allowing mirrors to be specified on a per-architecture basis. Each config is a dictionary which must have an entry for `arches`, specifying which architectures that config entry is for. The keyword `default` applies to any architecture not explicitly listed. The mirror url can be specified with the `uri` key, or a list of mirrors to check can be provided in order, with the first mirror that can be resolved being selected. This allows the same configuration to be used in different environment, with different hosts used for a local APT mirror. If no mirror is provided by `uri` or `search`, `search_dns` may be used to search for dns names in the format `<distro>-mirror` in each of the following:

- fqdn of this host per cloud metadata,
- `localdomain`,
- domains listed in `/etc/resolv.conf`.

If there is a dns entry for `<distro>-mirror`, then it is assumed that there is a distro mirror at `http://<distro>-mirror.<domain>/<distro>`. If the `primary` key is defined, but not the `security` key, then then configuration for `primary` is also used for `security`. If `search_dns` is used for the `security` key, the search pattern will be `<distro>-security-mirror`.

Each mirror may also specify a key to import via any of the following optional keys:

- `keyid`: a key to import via shortid or fingerprint.
- `key`: a raw PGP key.
- `keyserver`: alternate keyserver to pull `keyid` key from.

If no mirrors are specified, or all lookups fail, then default mirrors defined in the datasource are used. If none are present in the datasource either the following defaults are used:

- `primary => http://archive.ubuntu.com/ubuntu.`
- `security => http://security.ubuntu.com/ubuntu.`

Each object in **primary** list supports the following keys:

- arches:** (array of string)
- uri:** (string)
- search:** (array of string)
- search_dns:** (boolean)
- keyid:** (string)

key: (string)

keyserver: (string)

security: (array of object) Please refer to the primary config documentation.

Each object in **security** list supports the following keys:

arches: (array of string)

uri: (string)

search: (array of string)

search_dns: (boolean)

keyid: (string)

key: (string)

keyserver: (string)

add_apt_repo_match: (string) All source entries in `apt-sources` that match regex in `add_apt_repo_match` will be added to the system using `add-apt-repository`. If `add_apt_repo_match` is not specified, it defaults to `^\[w-\]++:\w`.

debconf_selections: (object) Debconf additional configurations can be specified as a dictionary under the `debconf_selections` config key, with each key in the dict representing a different set of configurations. The value of each key must be a string containing all the debconf configurations that must be applied. We will bundle all of the values and pass them to `debconf-set-selections`. Therefore, each value line must be a valid entry for `debconf-set-selections`, meaning that they must possess for distinct fields:

```
pkgname question type answer
```

Where:

- `pkgname` is the name of the package.
- `question` the name of the questions.
- `type` is the type of question.
- `answer` is the value used to answer the question.

For example: `ippackage ippackage/ip string 127.0.01.`

^.+\$: (string)

sources_list: (string) Specifies a custom template for rendering `sources.list`. If no `sources_list` template is given, cloud-init will use sane default. Within this template, the following strings will be replaced with the appropriate values:

- `$MIRROR`
- `$RELEASE`
- `$PRIMARY`
- `$SECURITY`
- `$KEY_FILE`.

conf: (string) Specify configuration for apt, such as proxy configuration. This configuration is specified as a string. For multiline APT configuration, make sure to follow yaml syntax.

https_proxy: (string) More convenient way to specify https APT proxy. https proxy url is specified in the format `https://[[user][:pass]@]host[:port]/`.

http_proxy: (string) More convenient way to specify http APT proxy. http proxy url is specified in the format `http://[[user][:pass]@]host[:port]/`.

proxy: (string) Alias for defining a http APT proxy.

ftp_proxy: (string) More convenient way to specify ftp APT proxy. ftp proxy url is specified in the format `ftp://[[user][:pass]@]host[:port]/`.

sources: (object) Source list entries can be specified as a dictionary under the `sources` config key, with each key in the dict representing a different source file. The key of each source entry will be used as an id that can be referenced in other config entries, as well as the filename for the source's configuration under `/etc/apt/sources.list.d`. If the name does not end with `.list`, it will be appended. If there is no configuration for a key in `sources`, no file will be written, but the key may still be referred to as an id in other `sources` entries.

Each entry under `sources` is a dictionary which may contain any of the following optional keys:

- **source:** a `sources.list` entry (some variable replacements apply).
- **keyid:** a key to import via shortid or fingerprint.
- **key:** a raw PGP key.
- **keyserver:** alternate keyserver to pull **keyid** key from.
- **filename:** specify the name of the list file.
- **append:** If `true`, append to `sources` file, otherwise overwrite it. Default: `true`.

The source key supports variable replacements for the following strings:

- `$MIRROR`
- `$PRIMARY`
- `$SECURITY`
- `$RELEASE`
- `$KEY_FILE`.

^.+\$: (object)

source: (string)

keyid: (string)

key: (string)

keyserver: (string)

filename: (string)

append: (boolean)

Examples:

```
apt:
  preserve_sources_list: false
  disable_suites:
    - $RELEASE-updates
    - backports
    - $RELEASE
    - mysuite
```

(continues on next page)

(continued from previous page)

```

primary:
  - arches:
    - amd64
    - i386
    - default
    uri: 'http://us.archive.ubuntu.com/ubuntu'
    search:
      - 'http://cool.but-sometimes-unreachable.com/ubuntu'
      - 'http://us.archive.ubuntu.com/ubuntu'
    search_dns: false
  - arches:
    - s390x
    - arm64
    uri: 'http://archive-to-use-for-arm64.example.com/ubuntu'

security:
  - arches:
    - default
    search_dns: true
sources_list: |
  deb $MIRROR $RELEASE main restricted
  deb-src $MIRROR $RELEASE main restricted
  deb $PRIMARY $RELEASE universe restricted
  deb $SECURITY $RELEASE-security multiverse
debconf_selections:
  set1: the-package the-package/some-flag boolean true
conf: |
  APT {
    Get {
      Assume-Yes 'true';
      Fix-Broken 'true';
    }
  }
proxy: 'http://[[user][:pass@]host[:port]/'
http_proxy: 'http://[[user][:pass@]host[:port]/'
ftp_proxy: 'ftp://[[user][:pass@]host[:port]/'
https_proxy: 'https://[[user][:pass@]host[:port]/'
sources:
  source1:
    keyid: 'keyid'
    keyserver: 'keyserverurl'
    source: 'deb [signed-by=$KEY_FILE] http://<url>/ bionic main'
  source2:
    source: 'ppa:<ppa-name>'
  source3:
    source: 'deb $MIRROR $RELEASE multiverse'
    key: |
      -----BEGIN PGP PUBLIC KEY BLOCK-----
      <key data>
      -----END PGP PUBLIC KEY BLOCK-----
  source4:
    source: 'deb $MIRROR $RELEASE multiverse'

```

(continues on next page)

(continued from previous page)

```
append: false
key: |
-----BEGIN PGP PUBLIC KEY BLOCK-----
<key data>
-----END PGP PUBLIC KEY BLOCK-----
```

2.17.4 Apt Pipelining

Summary: Configure apt pipelining

This module configures apt's `Acquire::http::Pipeline-Depth` option, which controls how apt handles HTTP pipelining. It may be useful for pipelining to be disabled, because some web servers, such as S3 do not pipeline properly (LP: #948461).

Value configuration options for this module are:

- `false` (Default): disable pipelining altogether
- `none`, `unchanged`, or `os`: use distro default
- `<number>`: Manually specify pipeline depth. This is not recommended.

Internal name: `cc_apt_pipelining`

Module frequency: once-per-instance

Supported distros: ubuntu, debian

Activate only on keys: `apt_pipelining`

Config schema:

`apt_pipelining`: (integer/boolean/none/unchanged/os)

Examples:

```
apt_pipelining: false
# --- Example2 ---
apt_pipelining: none
# --- Example3 ---
apt_pipelining: unchanged
# --- Example4 ---
apt_pipelining: os
# --- Example5 ---
apt_pipelining: 3
```

2.17.5 Bootcmd

Summary: Run arbitrary commands early in the boot process

This module runs arbitrary commands very early in the boot process, only slightly after a boothook would run. This is very similar to a boothook, but more user friendly. The environment variable `INSTANCE_ID` will be set to the current instance id for all run commands. Commands can be specified either as lists or strings. For invocation details, see `runcmd`.

Note: `bootcmd` should only be used for things that could not be done later in the boot process.

Note: when writing files, do not use /tmp dir as it races with systemd-tmpfiles-clean LP: #1707222. Use /run/somedir instead.

Internal name: cc_bootcmd

Module frequency: always

Supported distros: all

Activate only on keys: bootcmd

Config schema:

bootcmd: (array of (array of string/string))

Examples:

```
bootcmd:
- echo 192.168.1.130 us.archive.ubuntu.com > /etc/hosts
- [ cloud-init-per, once, mymkfs, mkfs, /dev/vdb ]
```

2.17.6 Byobu

Summary: Enable/disable byobu system wide and for default user

This module controls whether byobu is enabled or disabled system wide and for the default system user. If byobu is to be enabled, this module will ensure it is installed. Likewise, if it is to be disabled, it will be removed if installed.

Valid configuration options for this module are:

- **enable-system:** enable byobu system wide
- **enable-user:** enable byobu for the default user
- **disable-system:** disable byobu system wide
- **disable-user:** disable byobu for the default user
- **enable:** enable byobu both system wide and for default user
- **disable:** disable byobu for all users
- **user:** alias for enable-user
- **system:** alias for enable-system

Internal name: cc_byobu

Module frequency: once-per-instance

Supported distros: ubuntu, debian

Config schema:

byobu_by_default: (enable-system/enable-user/disable-system/disable-user/enable/disable/user/system)

Examples:

```
byobu_by_default: enable-user
# --- Example2 ---
byobu_by_default: disable-system
```

2.17.7 CA Certificates

Summary: Add ca certificates

This module adds CA certificates to `/etc/ca-certificates.conf` and updates the ssl cert cache using `update-ca-certificates`. The default certificates can be removed from the system with the configuration option `remove_defaults`.

Note: certificates must be specified using valid yaml. in order to specify a multiline certificate, the yaml multiline list syntax must be used

Note: For Alpine Linux the “`remove_defaults`” functionality works if the `ca-certificates` package is installed but not if the `ca-certificates-bundle` package is installed.

Internal name: `cc_ca_certs`

Module frequency: once-per-instance

Supported distros: alpine, debian, ubuntu, rhel

Activate only on keys: `ca_certs`, `ca-certs`

Config schema:

ca_certs: (object)

remove_defaults: (boolean) DEPRECATED: Dropped after April 2027. Use `remove_defaults`.

remove_defaults: (boolean) Remove default CA certificates if true. Default: false.

trusted: (array of string) List of trusted CA certificates to add.

ca-certs: (object) DEPRECATED: Dropped after April 2027. Use `ca_certs`.

remove_defaults: (boolean) DEPRECATED: Dropped after April 2027. Use `remove_defaults`.

remove_defaults: (boolean) Remove default CA certificates if true. Default: false.

trusted: (array of string) List of trusted CA certificates to add.

Examples:

```
ca_certs:
  remove_defaults: true
  trusted:
    - single_line_cert
    - |
      -----BEGIN CERTIFICATE-----
      YOUR-ORGS-TRUSTED-CA-CERT-HERE
      -----END CERTIFICATE-----
```

2.17.8 Chef

Summary: module that configures, starts and installs chef

This module enables chef to be installed (from packages, gems, or from omnibus). Before this occurs, chef configuration is written to disk (validation.pem, client.pem, firstboot.json, client.rb), and required directories are created (/etc/chef and /var/log/chef and so-on). If configured, chef will be installed and started in either daemon or non-daemon mode. If run in non-daemon mode, post run actions are executed to do finishing activities such as removing validation.pem.

Internal name: cc_chef

Module frequency: always

Supported distros: all

Activate only on keys: chef

Config schema:

chef: (object)

directories: (array of string) Create the necessary directories for chef to run. By default, it creates the following directories:

- /etc/chef
- /var/log/chef
- /var/lib/chef
- /var/cache/chef
- /var/backups/chef
- /var/run/chef.

validation_cert: (string) Optional string to be written to file validation_key. Special value `system` means set use existing file.

validation_key: (string) Optional path for validation_cert. default to `/etc/chef/validation.pem`.

firstboot_path: (string) Path to write run_list and initial_attributes keys that should also be present in this configuration, defaults to `/etc/chef/firstboot.json`.

exec: (boolean) Set true if we should run or not run chef (defaults to false, unless a gem installed is requested where this will then default to true).

client_key: (string) Optional path for client_cert. Default to `/etc/chef/client.pem`.

encrypted_data_bag_secret: (string) Specifies the location of the secret key used by chef to encrypt data items. By default, this path is set to null, meaning that chef will have to look at the path `/etc/chef/encrypted_data_bag_secret` for it.

environment: (string) Specifies which environment chef will use. By default, it will use the `_default` configuration.

file_backup_path: (string) Specifies the location in which backup files are stored. By default, it uses the `/var/backups/chef` location.

file_cache_path: (string) Specifies the location in which chef cache files will be saved. By default, it uses the `/var/cache/chef` location.

json_attribs: (string) Specifies the location in which some chef json data is stored. By default, it uses the `/etc/chef/firstboot.json` location.

log_level: (string) Defines the level of logging to be stored in the log file. By default this value is set to `:info`.

log_location: (string) Specifies the location of the chef log file. By default, the location is specified at `/var/log/chef/client.log`.

node_name: (string) The name of the node to run. By default, we will use the instance id as the node name.

omnibus_url: (string) Omnibus URL if chef should be installed through Omnibus. By default, it uses the `https://www.chef.io/chef/install.sh`.

omnibus_url_retries: (integer) The number of retries that will be attempted to reach the Omnibus URL. Default is 5.

omnibus_version: (string) Optional version string to require for omnibus install.

pid_file: (string) The location in which a process identification number (pid) is saved. By default, it saves in the `/var/run/chef/client.pid` location.

server_url: (string) The URL for the chef server.

show_time: (boolean) Show time in chef logs.

ssl_verify_mode: (string) Set the verify mode for HTTPS requests. We can have two possible values for this parameter:

- `:verify_none`: No validation of SSL certificates.
- `:verify_peer`: Validate all SSL certificates.

By default, the parameter is set as `:verify_none`.

validation_name: (string) The name of the chef-validator key that Chef Infra Client uses to access the Chef Infra Server during the initial Chef Infra Client run.

force_install: (boolean) If set to `true`, forces chef installation, even if it is already installed.

initial_attributes: (object of string) Specify a list of initial attributes used by the cookbooks.

install_type: (packages/gems/omnibus) The type of installation for chef. It can be one of the following values:

- `packages`
- `gems`
- `omnibus`.

run_list: (array of string) A run list for a first boot json.

chef_license: (string) string that indicates if user accepts or not license related to some of chef products.

Examples:

```
chef:
  directories:
    - /etc/chef
    - /var/log/chef
  validation_cert: system
  install_type: omnibus
  initial_attributes:
    apache:
      prefork:
        maxclients: 100
      keepalive: off
```

(continues on next page)

(continued from previous page)

```

run_list:
  - recipe[apache2]
  - role[db]
encrypted_data_bag_secret: /etc/chef/encrypted_data_bag_secret
environment: _default
log_level: :auto
omnibus_url_retries: 2
server_url: https://chef.yourorg.com:4000
ssl_verify_mode: :verify_peer
validation_name: yourorg-validator

```

2.17.9 Disable EC2 Metadata

Summary: Disable AWS EC2 Metadata

This module can disable the ec2 datasource by rejecting the route to 169.254.169.254, the usual route to the data-source. This module is disabled by default.

Internal name: cc_disable_ec2_metadata

Module frequency: always

Supported distros: all

Activate only on keys: disable_ec2_metadata

Config schema:

disable_ec2_metadata: (boolean) Set true to disable IPv4 routes to EC2 metadata. Default: false.

Examples:

```
disable_ec2_metadata: true
```

2.17.10 Disk Setup

Summary: Configure partitions and filesystems

This module is able to configure simple partition tables and filesystems.

Note: for more detail about configuration options for disk setup, see the disk setup example

Note: if a swap partition is being created via `disk_setup` then a `fs_entry` entry is also needed in order for `mkswap` to be run, otherwise when swap activation is later attempted it will fail.

For convenience, aliases can be specified for disks using the `device_aliases` config key, which takes a dictionary of alias: path mappings. There are automatic aliases for `swap` and `ephemeral<X>`, where `swap` will always refer to the active swap partition and `ephemeral<X>` will refer to the block device of the ephemeral image.

Disk partitioning is done using the `disk_setup` directive. This config directive accepts a dictionary where each key is either a path to a block device or an alias specified in `device_aliases`, and each value is the configuration options for the device. File system configuration is done using the `fs_setup` directive. This config directive accepts a list of filesystem configs.

Internal name: cc_disk_setup

Module frequency: once-per-instance

Supported distros: all

Activate only on keys: disk_setup, fs_setup

Config schema:

device_aliases: (object)

<alias_name>: (string) Path to disk to be aliased by this name.

disk_setup: (object)

<alias name/path>: (object)

table_type: (mbr/gpt) Specifies the partition table type, either mbr or gpt. Default: mbr.

layout: (remove/boolean/array) If set to **true**, a single partition using all the space on the device will be created. If set to **false**, no partitions will be created. If set to **remove**, any existing partition table will be purged. Partitions can be specified by providing a list to **layout**, where each entry in the list is either a size or a list containing a size and the numerical value for a partition type. The size for partitions is specified in **percentage** of disk space, not in bytes (e.g. a size of 33 would take up 1/3 of the disk space). The partition type defaults to '83' (Linux partition), for other types of partition, such as Linux swap, the type must be passed as part of a list along with the size. Default: **false**.

overwrite: (boolean) Controls whether this module tries to be safe about writing partition tables or not. If **overwrite: false** is set, the device will be checked for a partition table and for a file system and if either is found, the operation will be skipped. If **overwrite: true** is set, no checks will be performed. Using **overwrite: true** is **dangerous** and can lead to data loss, so double check that the correct device has been specified if using this option. Default: **false**.

fs_setup: (array of object)

Each object in **fs_setup** list supports the following keys:

label: (string) Label for the filesystem.

filesystem: (string) Filesystem type to create. E.g., **ext4** or **btrfs**.

device: (string) Specified either as a path or as an alias in the format **<alias name>.<y>** where **<y>** denotes the partition number on the device. If specifying device using the **<device name>.<partition number>** format, the value of **partition** will be overwritten.

partition: (string/integer/auto/any/none) The partition can be specified by setting **partition** to the desired partition number. The **partition** option may also be set to **auto**, in which this module will search for the existence of a filesystem matching the **label**, **type** and **device** of the **fs_setup** entry and will skip creating the filesystem if one is found. The **partition** option may also be set to **any**, in which case any file system that matches **type** and **device** will cause this module to skip filesystem creation for the **fs_setup** entry, regardless of **label** matching or not. To write a filesystem directly to a device, use **partition: none**. **partition: none** will **always** write the filesystem, even when the **label** and **filesystem** are matched, and **overwrite** is **false**.

overwrite: (boolean) If **true**, overwrite any existing filesystem. Using **overwrite: true** for filesystems is **dangerous** and can lead to data loss, so double check the entry in **fs_setup**. Default: **false**.

replace_fs: (string) Ignored unless **partition** is **auto** or **any**. Default **false**.

extra_opts: (string/array of string) Optional options to pass to the filesystem creation command. Ignored if you using `cmd` directly.

cmd: (string/array of string) Optional command to run to create the filesystem. Can include string substitutions of the other `fs_setup` config keys. This is only necessary if you need to override the default command.

Examples:

```
device_aliases:
  my_alias: /dev/sdb
  swap_disk: /dev/sdc
disk_setup:
  my_alias:
    table_type: gpt
    layout: [50, 50]
    overwrite: true
  swap_disk:
    table_type: gpt
    layout: [[100, 82]]
    overwrite: true
fs_setup:
- label: fs1
  filesystem: ext4
  device: my_alias.1
  cmd: mkfs -t %(filesystem)s -L %(label)s %(device)s
- label: fs2
  device: my_alias.2
  filesystem: ext4
- label: swap
  device: swap_disk.1
  filesystem: swap
mounts:
- ["my_alias.1", "/mnt1"]
- ["my_alias.2", "/mnt2"]
- ["swap_disk.1", "none", "swap", "sw", "0", "0"]
```

2.17.11 Fan

Summary: Configure ubuntu fan networking

This module installs, configures and starts the ubuntu fan network system. For more information about Ubuntu Fan, see: <https://wiki.ubuntu.com/FanNetworking>.

If cloud-init sees a `fan` entry in cloud-config it will:

- write `config_path` with the contents of the `config` key
- install the package `ubuntu-fan` if it is not installed
- ensure the service is started (or restarted if was previously running)

Additionally, the `ubuntu-fan` package will be automatically installed if not present.

Internal name: `cc_fan`

Module frequency: once-per-instance

Supported distros: ubuntu

Activate only on keys: fan

Config schema:

fan: (object)

config: (string) The fan configuration to use as a single multi-line string.

config_path: (string) The path to write the fan configuration to. Default: `/etc/network/fan`.

Examples:

```
fan:
  config: |
    # fan 240
    10.0.0.0/8 eth0/16 dhcp
    10.0.0.0/8 eth1/16 dhcp off
    # fan 241
    241.0.0.0/8 eth0/16 dhcp
  config_path: /etc/network/fan
```

2.17.12 Final Message

Summary: Output final message when cloud-init has finished

This module configures the final message that cloud-init writes. The message is specified as a jinja template with the following variables set:

- **version:** cloud-init version
- **timestamp:** time at cloud-init finish
- **datasource:** cloud-init data source
- **uptime:** system uptime

This message is written to the cloud-init log (usually `/var/log/cloud-init.log`) as well as stderr (which usually redirects to `/var/log/cloud-init-output.log`).

Upon exit, this module writes the system uptime, timestamp, and cloud-init version to `/var/lib/cloud/instance/boot-finished` independent of any user data specified for this module.

Internal name: `cc_final_message`

Module frequency: always

Supported distros: all

Config schema:

final_message: (string) The message to display at the end of the run.

Examples:

```
final_message: |
  cloud-init has finished
  version: $version
  timestamp: $timestamp
  datasource: $datasource
  uptime: $uptime
```

2.17.13 Growpart

Summary: Grow partitions

Growpart resizes partitions to fill the available disk space. This is useful for cloud instances with a larger amount of disk space available than the pristine image uses, as it allows the instance to automatically make use of the extra space.

The devices on which to run growpart are specified as a list under the `devices` key.

There is some functionality overlap between this module and the `growroot` functionality of `cloud-initramfs-tools`. However, there are some situations where one tool is able to function and the other is not. The default configuration for both should work for most cloud instances. To explicitly prevent `cloud-initramfs-tools` from running `growroot`, the file `/etc/growroot-disabled` can be created. By default, both `growroot` and `cc_growpart` will check for the existence of this file and will not run if it is present. However, this file can be ignored for `cc_growpart` by setting `ignore_growroot_disabled` to `true`. For more information on `cloud-initramfs-tools` see: <https://launchpad.net/cloud-initramfs-tools>

Growpart is enabled by default on the root partition. The default config for growpart is:

```
growpart:
  mode: auto
  devices: ["/"]
  ignore_growroot_disabled: false
```

Internal name: `cc_growpart`

Module frequency: `always`

Supported distros: `all`

Config schema:

growpart: (object)

mode: (auto/growpart/gpart/off) The utility to use for resizing. Default: `auto`

Possible options:

- `auto` - Use any available utility
- `growpart` - Use growpart utility
- `gpart` - Use BSD gpart utility
- `off` - Take no action. DEPRECATED: Specifying a boolean `false` value for this key is deprecated. Use `off` instead.

devices: (array of string) The devices to resize. Each entry can either be the path to the device's mountpoint in the filesystem or a path to the block device in `'/dev'`. Default: `[/]`.

ignore_growroot_disabled: (boolean) If `true`, ignore the presence of `/etc/growroot-disabled`. If `false` and the file exists, then don't resize. Default: `false`.

Examples:

```
growpart:
  mode: auto
  devices: ["/"]
  ignore_growroot_disabled: false

# --- Example2 ---
growpart:
```

(continues on next page)

(continued from previous page)

```
mode: growpart
devices:
- "/"
- "/dev/vdb1"
ignore_growroot_disabled: true
```

2.17.14 Grub Dpkg

Summary: Configure grub debconf installation device

Configure which device is used as the target for grub installation. This module can be enabled/disabled using the enabled config key in the `grub_dpkg` config dict. The global config key `grub-dpkg` is an alias for `grub_dpkg`. If no installation device is specified this module will execute `grub-probe` to determine which disk the `/boot` directory is associated with.

The value which is placed into the debconf database is in the format which the grub postinstall script expects. Normally, this is a `/dev/disk/by-id/` value, but we do fallback to the plain disk name if a by-id name is not present.

If this module is executed inside a container, then the debconf database is seeded with empty values, and `install_devices_empty` is set to true.

Internal name: `cc_grub_dpkg`

Module frequency: once-per-instance

Supported distros: ubuntu, debian

Config schema:

grub_dpkg: (object)

enabled: (boolean) Whether to configure which device is used as the target for grub installation. Default: `true`.

grub-pc/install_devices: (string) Device to use as target for grub installation. If unspecified, `grub-probe` of `/boot` will be used to find the device.

grub-pc/install_devices_empty: (boolean) Sets values for `grub-pc/install_devices_empty`. If unspecified, will be set to `true` if `grub-pc/install_devices` is empty, otherwise `false`. DEPRECATED: Use a boolean value instead.

grub-dpkg: (object) DEPRECATED: Use `grub_dpkg` instead.

Examples:

```
grub_dpkg:
  enabled: true
  grub-pc/install_devices: /dev/sda
  grub-pc/install_devices_empty: false
```

2.17.15 Install Hotplug

Summary: Install hotplug udev rules if supported and enabled

This module will install the udev rules to enable hotplug if supported by the datasource and enabled in the userdata. The udev rules will be installed as `/etc/udev/rules.d/10-cloud-init-hook-hotplug.rules`.

When hotplug is enabled, newly added network devices will be added to the system by cloud-init. After udev detects the event, cloud-init will refresh the instance metadata from the datasource, detect the device in the updated metadata, then apply the updated network configuration.

Currently supported datasources: Openstack, EC2

Internal name: `cc_install_hotplug`

Module frequency: once-per-instance

Supported distros: all

Config schema:

updates: (object)

network: (object)

when: (array of string)

Examples:

```
# Enable hotplug of network devices
updates:
  network:
    when: ["hotplug"]

# --- Example2 ---
# Enable network hotplug alongside boot event
updates:
  network:
    when: ["boot", "hotplug"]
```

2.17.16 Keyboard

Summary: Set keyboard layout

Handle keyboard configuration.

Internal name: `cc_keyboard`

Module frequency: once-per-instance

Supported distros: arch, debian, ubuntu, almalinux, amazon, centos, cloudlinux, eurolinux, fedora, mariner, miraclelinux, openEuler, openmandriva, photon, rhel, rocky, virtuozone, opensuse, sles

Activate only on keys: keyboard

Config schema:

keyboard: (object)

layout: (string) Required. Keyboard layout. Corresponds to XKBLAYOUT.

model: (string) Optional. Keyboard model. Corresponds to XKBMODEL. Default: `pc105`.

variant: (string) Optional. Keyboard variant. Corresponds to XKBVARIANT.

options: (string) Optional. Keyboard options. Corresponds to XKBOPTIONS.

Examples:

```
# Set keyboard layout to "us"
keyboard:
  layout: us

# --- Example2 ---
# Set specific keyboard layout, model, variant, options
keyboard:
  layout: de
  model: pc105
  variant: nodeadkeys
  options: compose:rwin
```

2.17.17 Keys to Console

Summary: Control which SSH host keys may be written to console

For security reasons it may be desirable not to write SSH host keys and their fingerprints to the console. To avoid either being written to the console the `emit_keys_to_console` config key under the main `ssh` config key can be used. To avoid the fingerprint of types of SSH host keys being written to console the `ssh_fp_console_blacklist` config key can be used. By default, all types of keys will have their fingerprints written to console. To avoid host keys of a key type being written to console the `ssh_key_console_blacklist` config key can be used. By default, `ssh-dss` host keys are not written to console.

Internal name: `cc_keys_to_console`

Module frequency: once-per-instance

Supported distros: all

Config schema:

ssh: (object)

emit_keys_to_console: (boolean) Set false to avoid printing SSH keys to system console. Default: true.

ssh_key_console_blacklist: (array of string) Avoid printing matching SSH key types to the system console.

ssh_fp_console_blacklist: (array of string) Avoid printing matching SSH fingerprints to the system console.

Examples:

```
# Do not print any SSH keys to system console
ssh:
  emit_keys_to_console: false

# --- Example2 ---
# Do not print certain ssh key types to console
ssh_key_console_blacklist: [dsa, ssh-dss]

# --- Example3 ---
# Do not print specific ssh key fingerprints to console
ssh_fp_console_blacklist:
- E25451E0221B5773DEBFF178ECDACB160995AA89
- FE76292D55E8B28EE6DB2B34B2D8A784F8C0AAB0
```

2.17.18 Landscape

Summary: Install and configure landscape client

This module installs and configures `landscape-client`. The landscape client will only be installed if the key `landscape` is present in config. Landscape client configuration is given under the `client` key under the main `landscape` config key. The config parameters are not interpreted by cloud-init, but rather are converted into a ConfigObj formatted file and written out to the `[client]` section in `/etc/landscape/client.conf`.

The following default client config is provided, but can be overridden:

```
landscape:
  client:
    log_level: "info"
    url: "https://landscape.canonical.com/message-system"
    ping_url: "http://landscape.canonical.com/ping"
    data_path: "/var/lib/landscape/client"
```

Note: see landscape documentation for client config keys

Note: if `tags` is defined, its contents should be a string delimited with `,` rather than a list

Internal name: `cc_landscape`

Module frequency: once-per-instance

Supported distros: ubuntu

Activate only on keys: `landscape`

Config schema:

landscape: (object)

client: (object)

url: (string) The Landscape server URL to connect to. Default: `https://landscape.canonical.com/message-system`.

ping_url: (string) The URL to perform lightweight exchange initiation with. Default: `https://landscape.canonical.com/ping`.

data_path: (string) The directory to store data files in. Default: `/var/lib/landscape/client/`.

log_level: (debug/info/warning/error/critical) The log level for the client. Default: `info`.

computer_title: (string) The title of this computer.

account_name: (string) The account this computer belongs to.

registration_key: (string) The account-wide key used for registering clients.

tags: (string) Comma separated list of tag names to be sent to the server.

http_proxy: (string) The URL of the HTTP proxy, if one is needed.

https_proxy: (string) The URL of the HTTPS proxy, if one is needed.

Examples:

```
# To discover additional supported client keys, run
# man landscape-config.
landscape:
  client:
    url: "https://landscape.canonical.com/message-system"
    ping_url: "http://landscape.canonical.com/ping"
    data_path: "/var/lib/landscape/client"
    http_proxy: "http://my.proxy.com/foobar"
    https_proxy: "https://my.proxy.com/foobar"
    tags: "server,cloud"
    computer_title: "footitle"
    registration_key: "fookey"
    account_name: "fooaccount"

# --- Example2 ---
# Any keys below `client` are optional and the default values will
# be used.
landscape:
  client: {}
```

2.17.19 Locale

Summary: Set system locale

Configure the system locale and apply it system wide. By default use the locale specified by the datasource.

Internal name: cc_locale

Module frequency: once-per-instance

Supported distros: all

Config schema:

locale: (string) The locale to set as the system's locale (e.g. ar_PS).

locale_configfile: (string) The file in which to write the locale configuration (defaults to the distro's default location).

Examples:

```
# Set the locale to ar_AE
locale: ar_AE

# --- Example2 ---
# Set the locale to fr_CA in /etc/alternate_path/locale
locale: fr_CA
locale_configfile: /etc/alternate_path/locale
```


2.17.20 LXD

Summary: Configure LXD with `lxd init` and optionally `lxd-bridge`

This module configures `lxd` with user specified options using `lxd init`. If `lxd` is not present on the system but `lxd` configuration is provided, then `lxd` will be installed. If the selected storage backend userspace utility is not installed, it will be installed. If network bridge configuration is provided, then `lxd-bridge` will be configured accordingly.

Internal name: `cc_lxd`

Module frequency: once-per-instance

Supported distros: ubuntu

Activate only on keys: `lxd`

Config schema:

lxd: (object)

init: (object) LXD init configuration values to provide to `lxd init --auto` command. Can not be combined with `lxd.preseed`.

network_address: (string) IP address for LXD to listen on.

network_port: (integer) Network port to bind LXD to.

storage_backend: (zfs/dir/lvm/btrfs) Storage backend to use. Default: `dir`.

storage_create_device: (string) Setup device based storage using `DEVICE`.

storage_create_loop: (integer) Setup loop based storage with `SIZE` in GB.

storage_pool: (string) Name of storage pool to use or create.

trust_password: (string) The password required to add new clients.

bridge: (object) LXD bridge configuration provided to setup the host `lxd` bridge. Can not be combined with `lxd.preseed`.

mode: (none/existing/new) Whether to setup LXD bridge, use an existing bridge by `name` or create a new bridge. `none` will avoid bridge setup, `existing` will configure `lxd` to use the bring matching `name` and `new` will create a new bridge.

name: (string) Name of the LXD network bridge to attach or create. Default: `lxdbr0`.

mtu: (integer) Bridge MTU, defaults to LXD's default value.

ipv4_address: (string) IPv4 address for the bridge. If set, `ipv4_netmask` key required.

ipv4_netmask: (integer) Prefix length for the `ipv4_address` key. Required when `ipv4_address` is set.

ipv4_dhcp_first: (string) First IPv4 address of the DHCP range for the network created. This value will combined with `ipv4_dhcp_last` key to set LXC `ipv4.dhcp.ranges`.

ipv4_dhcp_last: (string) Last IPv4 address of the DHCP range for the network created. This value will combined with `ipv4_dhcp_first` key to set LXC `ipv4.dhcp.ranges`.

ipv4_dhcp_leases: (integer) Number of DHCP leases to allocate within the range. Automatically calculated based on `ipv4_dhcp_first` and `ipv4_dhcp_last` when unset.

ipv4_nat: (boolean) Set `true` to NAT the IPv4 traffic allowing for a routed IPv4 network. Default: `false`.

ipv6_address: (string) IPv6 address for the bridge (CIDR notation). When set, `ipv6_netmask` key is required. When absent, no IPv6 will be configured.

ipv6_netmask: (integer) Prefix length for `ipv6_address` provided. Required when `ipv6_address` is set.

ipv6_nat: (boolean) Whether to NAT. Default: `false`.

domain: (string) Domain to advertise to DHCP clients and use for DNS resolution.

preseed: (string) Opaque LXD preseed YAML config passed via stdin to the command: `lxd init --preseed`. See: <https://linuxcontainers.org/lxd/docs/master/preseed/> or `lxd init --dump` for viable config. Can not be combined with either `lxd.init` or `lxd.bridge`.

Examples:

```
# Simplest working directory backed LXD configuration
lxd:
  init:
    storage_backend: dir

# --- Example2 ---
# LXD init showcasing cloud-init's LXD config options
lxd:
  init:
    network_address: 0.0.0.0
    network_port: 8443
    storage_backend: zfs
    storage_pool: datapool
    storage_create_loop: 10
  bridge:
    mode: new
    mtu: 1500
    name: lxdbr0
    ipv4_address: 10.0.8.1
    ipv4_netmask: 24
    ipv4_dhcp_first: 10.0.8.2
    ipv4_dhcp_last: 10.0.8.3
    ipv4_dhcp_leases: 250
    ipv4_nat: true
    ipv6_address: fd98:9e0:3744::1
    ipv6_netmask: 64
    ipv6_nat: true
    domain: lxd

# --- Example3 ---
# For more complex non-interactive LXD configuration of networks,
# storage_pools, profiles, projects, clusters and core config,
# `lxd:preseed` config will be passed as stdin to the command:
# lxd init --preseed
# See https://linuxcontainers.org/lxd/docs/master/preseed/ or
# run: lxd init --dump to see viable preseed YAML allowed.
#
# Preseed settings configuring the LXD daemon for HTTPS connections
# on 192.168.1.1 port 9999, a nested profile which allows for
# LXD nesting on containers and a limited project allowing for
# RBAC approach when defining behavior for sub projects.
lxd:
```

(continues on next page)

(continued from previous page)

```

preseed: |
  config:
    core.https_address: 192.168.1.1:9999
  networks:
    - config:
        ipv4.address: 10.42.42.1/24
        ipv4.nat: true
        ipv6.address: fd42:4242:4242:4242::1/64
        ipv6.nat: true
        description: ""
        name: lxdbr0
        type: bridge
        project: default
  storage_pools:
    - config:
        size: 5GiB
        source: /var/snap/lxd/common/lxd/disks/default.img
        description: ""
        name: default
        driver: zfs
  profiles:
    - config: {}
      description: Default LXD profile
      devices:
        eth0:
          name: eth0
          network: lxdbr0
          type: nic
        root:
          path: /
          pool: default
          type: disk
      name: default
    - config: {}
      security.nesting: true
      devices:
        eth0:
          name: eth0
          network: lxdbr0
          type: nic
        root:
          path: /
          pool: default
          type: disk
      name: nested
  projects:
    - config:
        features.images: true
        features.networks: true
        features.profiles: true
        features.storage.volumes: true
        description: Default LXD project

```

(continues on next page)

(continued from previous page)

```
name: default
- config:
  features.images: false
  features.networks: true
  features.profiles: false
  features.storage.volumes: false
description: Limited Access LXD project
name: limited
```

2.17.21 Mcollective

Summary: Install, configure and start mcollective

This module installs, configures and starts mcollective. If the `mcollective` key is present in `config`, then mcollective will be installed and started.

Configuration for mcollective can be specified in the `conf` key under `mcollective`. Each `config` value consists of a key value pair and will be written to `/etc/mcollective/server.cfg`. The `public-cert` and `private-cert` keys, if present in `conf` may be used to specify the public and private certificates for mcollective. Their values will be written to `/etc/mcollective/ssl/server-public.pem` and `/etc/mcollective/ssl/server-private.pem`.

Note: The `ec2` metadata service is readable by non-root users. If security is a concern, use `include-once` and `ssl` urls.

Internal name: `cc_mcollective`

Module frequency: once-per-instance

Supported distros: all

Activate only on keys: `mcollective`

Config schema:

mcollective: (object)

conf: (object)

public-cert: (string) Optional value of server public certificate which will be written to `/etc/mcollective/ssl/server-public.pem`.

private-cert: (string) Optional value of server private certificate which will be written to `/etc/mcollective/ssl/server-private.pem`.

`^.+$.:` (boolean/integer/string) Optional config key: value pairs which will be appended to `/etc/mcollective/server.cfg`.

Examples:

```
# Provide server private and public key and provide the following
# config settings in /etc/mcollective/server.cfg:
# loglevel: debug
# plugin.stomp.host: dbhost

# WARNING WARNING WARNING
# The ec2 metadata service is a network service, and thus is
# readable by non-root users on the system
```

(continues on next page)

(continued from previous page)

```
# (ie: 'ec2metadata --user-data')
# If you want security for this, please use include-once + SSL urls
mcollective:
  conf:
    loglevel: debug
    plugin.stomp.host: dbhost
    public-cert: |
      -----BEGIN CERTIFICATE-----
      <cert data>
      -----END CERTIFICATE-----
    private-cert: |
      -----BEGIN CERTIFICATE-----
      <cert data>
      -----END CERTIFICATE-----
```

2.17.22 Migrator

Summary: Migrate old versions of cloud-init data to new

This module handles moving old versions of cloud-init data to newer ones. Currently, it only handles renaming cloud-init's per-frequency semaphore files to canonicalized name and renaming legacy semaphore names to newer ones. This module is enabled by default, but can be disabled by specifying `migrate: false` in config.

Internal name: `cc_migrator`

Module frequency: `always`

Supported distros: `all`

Config schema:

migrate: (boolean) Whether to migrate legacy cloud-init semaphores to new format. Default: `true`.

Examples:

```
# Do not migrate cloud-init semaphores
migrate: false
```

2.17.23 Mounts

Summary: Configure mount points and swap files

This module can add or remove mountpoints from `/etc/fstab` as well as configure swap. The `mounts` config key takes a list of fstab entries to add. Each entry is specified as a list of `[fs_spec, fs_file, fs_vfstype, fs_mntops, fs_freq, fs_passno]`. For more information on these options, consult the manual for `/etc/fstab`. When specifying the `fs_spec`, if the device name starts with one of `xvd`, `sd`, `hd`, or `vd`, the leading `/dev` may be omitted.

Any mounts that do not appear to either an attached block device or network resource will be skipped with a log like "Ignoring nonexistent mount ...".

Cloud-init will attempt to add the following mount directives if available and unconfigured in `/etc/fstab`:

```
mounts:
  - ["ephemeral0", "/mnt", "auto", "defaults,nofail,x-systemd.requires=cloud-init.
```

(continues on next page)

(continued from previous page)

```
↪service", "0", "2"]
- ["swap", "none", "swap", "sw", "0", "0"]
```

In order to remove a previously listed mount, an entry can be added to the `mounts` list containing `fs_spec` for the device to be removed but no mountpoint (i.e. `[swap]` or `[swap, null]`).

The `mount_default_fields` config key allows default options to be specified for the values in a `mounts` entry that are not specified, aside from the `fs_spec` and the `fs_file`. If specified, this must be a list containing 6 values. It defaults to:

```
mount_default_fields: [none, none, "auto", "defaults,nofail,x-systemd.requires=cloud-init.
↪service", "0", "2"]
```

Non-systemd init systems will vary in `mount_default_fields`.

Swap files can be configured by setting the path to the swap file to create with `filename`, the size of the swap file with `size` maximum size of the swap file if using an `size: auto` with `maxsize`. By default no swap file is created.

Internal name: `cc_mounts`

Module frequency: once-per-instance

Supported distros: all

Config schema:

mounts: (array of array) List of lists. Each inner list entry is a list of `/etc/fstab` mount declarations of the format: `[fs_spec, fs_file, fs_vfstype, fs_mntops, fs-freq, fs_passno]`. A mount declaration with less than 6 items will get remaining values from `mount_default_fields`. A mount declaration with only `fs_spec` and no `fs_file` mountpoint will be skipped.

mount_default_fields: (array of (string/null)) Default mount configuration for any mount entry with less than 6 options provided. When specified, 6 items are required and represent `/etc/fstab` entries. Default: `defaults, nofail, x-systemd.requires=cloud-init.service, _netdev`.

swap: (object)

filename: (string) Path to the swap file to create.

size: (auto/integer/string) The size in bytes of the swap file, 'auto' or a human-readable size abbreviation of the format `<float_size><units>` where units are one of B, K, M, G or T.

maxsize: (integer/string) The maxsize in bytes of the swap file.

Examples:

```
# Mount ephemeral0 with "noexec" flag, /dev/sdc with mount_default_fields,
# and /dev/xvddh with custom fs_passno "0" to avoid fsck on the mount.
# Also provide an automatically sized swap with a max size of 10485760
# bytes.
mounts:
- [ /dev/ephemeral0, /mnt, auto, "defaults,noexec" ]
- [ sdc, /opt/data ]
- [ xvddh, /opt/data, auto, "defaults,nofail", "0", "0" ]
mount_default_fields: [None, None, auto, "defaults,nofail", "0", "2"]
swap:
  filename: /my/swapfile
  size: auto
  maxsize: 10485760
```

(continues on next page)

(continued from previous page)

```
# --- Example2 ---
# Create a 2 GB swap file at /swapfile using human-readable values
swap:
  filename: /swapfile
  size: 2G
  maxsize: 2G
```

2.17.24 NTP

Summary: enable and configure ntp

Handle ntp configuration. If ntp is not installed on the system and ntp configuration is specified, ntp will be installed. If there is a default ntp config file in the image or one is present in the distro's ntp package, it will be copied to a file with .dist appended to the filename before any changes are made. A list of ntp pools and ntp servers can be provided under the ntp config key. If no ntp servers or pools are provided, 4 pools will be used in the format {0-3}.{distro}.pool.ntp.org.

Internal name: cc_ntp

Module frequency: once-per-instance

Supported distros: almalinux, alpine, centos, cloudlinux, cos, debian, eurolinux, fedora, freebsd, mariner, miraclelinux, openbsd, openEuler, openmandriva, opensuse, photon, rhel, rocky, sles, ubuntu, virtuoizzo

Activate only on keys: ntp

Config schema:

ntp: (null/object)

pools: (array of string) List of ntp pools. If both pools and servers are empty, 4 default pool servers will be provided of the format {0-3}.{distro}.pool.ntp.org. NOTE: for Alpine Linux when using the Busybox NTP client this setting will be ignored due to the limited functionality of Busybox's ntpd.

servers: (array of string) List of ntp servers. If both pools and servers are empty, 4 default pool servers will be provided with the format {0-3}.{distro}.pool.ntp.org.

ntp_client: (string) Name of an NTP client to use to configure system NTP. When unprovided or 'auto' the default client preferred by the distribution will be used. The following built-in client names can be used to override existing configuration defaults: chrony, ntp, openntpd, ntpdate, systemd-timesyncd.

enabled: (boolean) Attempt to enable ntp clients if set to True. If set to False, ntp client will not be configured or installed.

config: (object) Configuration settings or overrides for the ntp_client specified.

confpath: (string) The path to where the ntp_client configuration is written.

check_exe: (string) The executable name for the ntp_client. For example, ntp service check_exe is 'ntpd' because it runs the ntpd binary.

packages: (array of string) List of packages needed to be installed for the selected ntp_client.

service_name: (string) The systemd or sysvinit service name used to start and stop the ntp_client service.

template: (string) Inline template allowing users to define their own `ntp_client` configuration template. The value must start with `## template:jinja` to enable use of templating support. .

Examples:

```
# Override ntp with chrony configuration on Ubuntu
ntp:
  enabled: true
  ntp_client: chrony # Uses cloud-init default chrony configuration

# --- Example2 ---
# Provide a custom ntp client configuration
ntp:
  enabled: true
  ntp_client: myntpcclient
  config:
    conffpath: /etc/myntpcclient/myntpcclient.conf
    check_exe: myntpcclientd
    packages:
      - myntpcclient
    service_name: myntpcclient
    template: |
      ## template:jinja
      # My NTP Client config
      {% if pools -%}# pools{% endif %}
      {% for pool in pools -%}
      pool {{pool}} iburst
      {% endfor %}
      {%- if servers %}# servers
      {% endif %}
      {% for server in servers -%}
      server {{server}} iburst
      {% endfor %}
  pools: [0.int.pool.ntp.org, 1.int.pool.ntp.org, ntp.myorg.org]
  servers:
    - ntp.server.local
    - ntp.ubuntu.com
    - 192.168.23.2
```

2.17.25 Package Update Upgrade Install

Summary: Update, upgrade, and install packages

This module allows packages to be updated, upgraded or installed during boot. If any packages are to be installed or an upgrade is to be performed then the package cache will be updated first. If a package installation or upgrade requires a reboot, then a reboot can be performed if `package_reboot_if_required` is specified.

Internal name: `cc_package_update_upgrade_install`

Module frequency: once-per-instance

Supported distros: all

Activate only on keys: `apt_update`, `package_update`, `apt_upgrade`, `package_upgrade`, `packages`

Config schema:

packages: (array of (array of string/string)) A list of packages to install. Each entry in the list can be either a package name or a list with two entries, the first being the package name and the second being the specific package version to install.

package_update: (boolean) Set true to update packages. Happens before upgrade or install. Default: false.

package_upgrade: (boolean) Set true to upgrade packages. Happens before install. Default: false.

package_reboot_if_required: (boolean) Set true to reboot the system if required by presence of */var/run/reboot-required*. Default: false.

apt_update: (boolean) DEPRECATED: Dropped after April 2027. Use `package_update`. Default: false.

apt_upgrade: (boolean) DEPRECATED: Dropped after April 2027. Use `package_upgrade`. Default: false.

apt_reboot_if_required: (boolean) DEPRECATED: Dropped after April 2027. Use `package_reboot_if_required`. Default: false.

Examples:

```
packages:
- pwgen
- pastebinit
- [libpython3.8, 3.8.10-0ubuntu1~20.04.2]
package_update: true
package_upgrade: true
package_reboot_if_required: true
```

2.17.26 Phone Home

Summary: Post data to url

This module can be used to post data to a remote host after boot is complete. If the post url contains the string `$INSTANCE_ID` it will be replaced with the id of the current instance. Either all data can be posted or a list of keys to post. Available keys are:

- `pub_key_dsa`
- `pub_key_rsa`
- `pub_key_ecdsa`
- `pub_key_ed25519`
- `instance_id`
- `hostname`
- `fdqn`

Data is sent as `x-www-form-urlencoded` arguments.

Example HTTP POST:

```
POST / HTTP/1.1
Content-Length: 1337
User-Agent: Cloud-Init/21.4
Accept-Encoding: gzip, deflate
Accept: */*
Content-Type: application/x-www-form-urlencoded
```

(continues on next page)

(continued from previous page)

```
pub_key_dsa=dsa_contents&pub_key_rsa=rsa_contents&pub_key_ecdsa=ecdsa_contents&pub_key_
↪ed25519=ed25519_contents&instance_id=i-87018aed&hostname=myhost&fqdn=myhost.internal
```

Internal name: cc_phone_home

Module frequency: once-per-instance

Supported distros: all

Activate only on keys: phone_home

Config schema:

phone_home: (object)

url: (string) The URL to send the phone home data to.

post: (all/array) A list of keys to post or all. Default: all.

tries: (integer) The number of times to try sending the phone home data. Default: 10.

Examples:

```
phone_home:
  url: http://example.com/$INSTANCE_ID/
  post: all

# --- Example2 ---
phone_home:
  url: http://example.com/$INSTANCE_ID/
  post:
    - pub_key_dsa
    - pub_key_rsa
    - pub_key_ecdsa
    - pub_key_ed25519
    - instance_id
    - hostname
    - fqdn
  tries: 5
```

2.17.27 Power State Change

Summary: Change power state

This module handles shutdown/reboot after all config modules have been run. By default it will take no action, and the system will keep running unless a package installation/upgrade requires a system reboot (e.g. installing a new kernel) and `package_reboot_if_required` is true.

Using this module ensures that cloud-init is entirely finished with modules that would be executed.

An example to distinguish delay from timeout:

If you delay 5 (5 minutes) and have a timeout of 120 (2 minutes), then the max time until shutdown will be 7 minutes, though it could be as soon as 5 minutes. Cloud-init will invoke ‘shutdown +5’ after the process finishes, or when ‘timeout’ seconds have elapsed.

Note: With Alpine Linux any message value specified is ignored as Alpine's halt, poweroff, and reboot commands do not support broadcasting a message.

Internal name: cc_power_state_change

Module frequency: once-per-instance

Supported distros: all

Activate only on keys: power_state

Config schema:

power_state: (object)

delay: (integer/now) Time in minutes to delay after cloud-init has finished. Can be now or an integer specifying the number of minutes to delay. Default: now. DEPRECATED: Use of string for this value will be dropped after April 2027. Use now or integer type.

mode: (poweroff/reboot/halt) Must be one of poweroff, halt, or reboot.

message: (string) Optional message to display to the user when the system is powering off or rebooting.

timeout: (integer) Time in seconds to wait for the cloud-init process to finish before executing shutdown. Default: 30.

condition: (string/boolean/array) Apply state change only if condition is met. May be boolean true (always met), false (never met), or a command string or list to be executed. For command formatting, see the documentation for cc_runcmd. If exit code is 0, condition is met, otherwise not. Default: true.

Examples:

```
power_state:
  delay: now
  mode: poweroff
  message: Powering off
  timeout: 2
  condition: true

# --- Example2 ---
power_state:
  delay: 30
  mode: reboot
  message: Rebooting machine
  condition: test -f /var/tmp/reboot_me
```

2.17.28 Puppet

Summary: Install, configure and start puppet

This module handles puppet installation and configuration. If the `puppet` key does not exist in global configuration, no action will be taken. If a config entry for `puppet` is present, then by default the latest version of puppet will be installed. If the `puppet` config key exists in the config archive, this module will attempt to start puppet even if no installation was performed.

The module also provides keys for configuring the new puppet 4 paths and installing the puppet package from the puppetlabs repositories: https://docs.puppet.com/puppet/4.2/reference/whered_it_go.html The keys are `package_name`, `conf_file`, `ssl_dir` and `csr_attributes_path`. If unset, their values will default to ones that work with puppet 3.x and with distributions that ship modified puppet 4.x that uses the old paths.

Internal name: `cc_puppet`

Module frequency: once-per-instance

Supported distros: all

Activate only on keys: `puppet`

Config schema:

puppet: (object)

install: (boolean) Whether or not to install puppet. Setting to `false` will result in an error if puppet is not already present on the system. Default: `true`.

version: (string) Optional version to pass to the installer script or package manager. If unset, the latest version from the repos will be installed.

install_type: (packages/aio) Valid values are `packages` and `aio`. Agent packages from the puppetlabs repositories can be installed by setting `aio`. Based on this setting, the default config/SSL/CSR paths will be adjusted accordingly. Default: `packages`.

collection: (string) Puppet collection to install if `install_type` is `aio`. This can be set to one of `puppet` (rolling release), `puppet6`, `puppet7` (or their nightly counterparts) in order to install specific release streams.

aio_install_url: (string) If `install_type` is `aio`, change the url of the install script.

cleanup: (boolean) Whether to remove the puppetlabs repo after installation if `install_type` is `aio` Default: `true`.

conf_file: (string) The path to the puppet config file. Default depends on `install_type`.

ssl_dir: (string) The path to the puppet SSL directory. Default depends on `install_type`.

csr_attributes_path: (string) The path to the puppet csr attributes file. Default depends on `install_type`.

package_name: (string) Name of the package to install if `install_type` is `packages`. Default: `puppet`.

exec: (boolean) Whether or not to run puppet after configuration finishes. A single manual run can be triggered by setting `exec` to `true`, and additional arguments can be passed to `puppet agent` via the `exec_args` key (by default the agent will execute with the `--test` flag). Default: `false`.

exec_args: (array of string) A list of arguments to pass to 'puppet agent' if 'exec' is true Default: `['--test']`.

start_service: (boolean) By default, the puppet service will be automatically enabled after installation and set to automatically start on boot. To override this in favor of manual puppet execution set `start_service` to `false`.

conf: (object) Every key present in the conf object will be added to puppet.conf. As such, section names should be one of: **main**, **server**, **agent** or **user** and keys should be valid puppet configuration options. The configuration is specified as a dictionary containing high-level <section> keys and lists of <key>=<value> pairs within each section. The **certname** key supports string substitutions for %i and %f, corresponding to the instance id and fqdn of the machine respectively.

ca_cert is a special case. It won't be added to puppet.conf. It holds the puppetserver certificate in pem format. It should be a multi-line string (using the | yml notation for multi-line strings).

main: (object)

server: (object)

agent: (object)

user: (object)

ca_cert: (string)

csr_attributes: (object) create a **csr_attributes.yml** file for CSR attributes and certificate extension requests. See https://puppet.com/docs/puppet/latest/config_file_csr_attributes.html.

custom_attributes: (object)

extension_requests: (object)

Examples:

```
puppet:
  install: true
  version: "7.7.0"
  install_type: "aio"
  collection: "puppet7"
  aio_install_url: 'https://git.io/JBhoQ'
  cleanup: true
  conf_file: "/etc/puppet/puppet.conf"
  ssl_dir: "/var/lib/puppet/ssl"
  csr_attributes_path: "/etc/puppet/csr_attributes.yml"
  exec: true
  exec_args: ['--test']
  conf:
    agent:
      server: "puppetserver.example.org"
      certname: "%i.%f"
    ca_cert: |
      -----BEGIN CERTIFICATE-----
      MIICCTCCAXKgAwIBAgIBATANBgkqhkiG9w0BAQUFADANMQswCQYDVQQDDAJjYTAe
      Fw0xMDAyMTUxNzI5MjFjFaFw0xNTAyMTQxNzI5MjFjFaMA0xCzAJBgNVBAMAMhMIGf
      MA0GCSqGSIb3DQEBAQUAA4GNADCBiQKBgQCu7Q40sm47/E1Pf+r8AYb/V/FWGPgc
      b0140mNoX7dgCxTDvps/h8Vw555PdAFsW5+QhsGr31IJNI3kSYprFQcYf7A8tNWu
      1MASW2CfaEiOEi9F1R3R4QlZ4ix+iNoHiUDTjazw/tZwEdxaQXQVLwgTGRwVa+aa
      qbutJKi93MILLwIDAQABo3kwdzA4BglghkgBhvhCAQ0EKEKxYpUHVwcGV0IFJ1YnkV
      T3B1b1NTTCBHZW51cmF0ZWQgQ2VydGhmaWNhdGUwDwYDVVR0TAQH/BAUwAwEB/zAd
      BgNVHQ4EFgQUu4+jHB+GYE5Vxo+ol10AhevspjAwCwYDVROpBAQDAgEGMA0GCSqG
      SIb3DQEBAQUAA4GBAH/rxlUIjwNb3n7TXJcDJ6MMHulwjr03BDJXKb34UlnkpaF
      +GAlzPXWa7b0908M9I8RnPFvtKnteLbvgTK+h+zX1XCty+S2EQWk29i2AdoQ0Txb
      hppiGMp0tT5Havu4aceCXiy2crVcudj3NFciy8X66SoECemW9UYDCb9T5D0d
      -----END CERTIFICATE-----
```

(continues on next page)

(continued from previous page)

```

csr_attributes:
  custom_attributes:
    1.2.840.113549.1.9.7: 342thbjkt82094y0uthhor289jnqthpc2290
  extension_requests:
    pp_uuid: ED803750-E3C7-44F5-BB08-41A04433FE2E
    pp_image_name: my_ami_image
    pp_preshared_key: 342thbjkt82094y0uthhor289jnqthpc2290

# --- Example2 ---
puppet:
  install_type: "packages"
  package_name: "puppet"
  exec: false

```

2.17.29 Resizefs

Summary: Resize filesystem

Resize a filesystem to use all available space on partition. This module is useful along with `cc_growpart` and will ensure that if the root partition has been resized the root filesystem will be resized along with it. By default, `cc_resizefs` will resize the root partition and will block the boot process while the resize command is running. Optionally, the resize operation can be performed in the background while cloud-init continues running modules. This can be enabled by setting `resize_rootfs` to `noblock`. This module can be disabled altogether by setting `resize_rootfs` to `false`.

Internal name: `cc_resizefs`

Module frequency: always

Supported distros: all

Config schema:

resize_rootfs: (true/false/noblock) Whether to resize the root partition. `noblock` will resize in the background. Default: `true`.

Examples:

```

resize_rootfs: false # disable root filesystem resize operation
# --- Example2 ---
resize_rootfs: noblock # runs resize operation in the background

```

2.17.30 Resolv Conf

Summary: Configure `resolv.conf`

This module is intended to manage `resolv.conf` in environments where early configuration of `resolv.conf` is necessary for further bootstrapping and/or where configuration management such as puppet or chef own DNS configuration. As Debian/Ubuntu will, by default, utilize `resolvconf`, and similarly Red Hat will use `sysconfig`, this module is likely to be of little use unless those are configured correctly.

When using a *Config Drive* and a RHEL-like system, `resolv.conf` will also be managed automatically due to the available information provided for DNS servers in the *Networking Config Version 2* format. For those that wish to have different settings, use this module.

In order for the `resolv_conf` section to be applied, `manage_resolv_conf` must be set `true`.

Note: For Red Hat with sysconfig, be sure to set PEERDNS=no for all DHCP enabled NICs.

Note: And, in Ubuntu/Debian it is recommended that DNS be configured via the standard /etc/network/interfaces configuration file.

Internal name: cc_resolv_conf

Module frequency: once-per-instance

Supported distros: alpine, fedora, mariner, opensuse, photon, rhel, sles

Activate only on keys: manage_resolv_conf

Config schema:

manage_resolv_conf: (boolean) Whether to manage the resolv.conf file. `resolv_conf` block will be ignored unless this is set to `true`. Default: `false`.

resolv_conf: (object)

nameservers: (array) A list of nameservers to use to be added as `nameserver` lines.

searchdomains: (array) A list of domains to be added `search` line.

domain: (string) The domain to be added as `domain` line.

sortlist: (array) A list of IP addresses to be added to `sortlist` line.

options: (object) Key/value pairs of options to go under `options` heading. A unary option should be specified as `true`.

Examples:

```
manage_resolv_conf: true
resolv_conf:
  nameservers:
    - 8.8.8.8
    - 8.8.4.4
  searchdomains:
    - foo.example.com
    - bar.example.com
  domain: example.com
  sortlist:
    - 10.0.0.1/255
    - 10.0.0.2
  options:
    rotate: true
    timeout: 1
```

2.17.31 Red Hat Subscription

Summary: Register Red Hat Enterprise Linux based system

Register a Red Hat system either by username and password *or* activation and org. Following a successful registration, you can:

- auto-attach subscriptions
- set the service level
- add subscriptions based on pool id
- enable/disable yum repositories based on repo id
- alter the rhsm_baseurl and server-hostname in `/etc/rhsm/rhsm.conf`.

Internal name: `cc_rh_subscription`

Module frequency: once-per-instance

Supported distros: fedora, rhel

Activate only on keys: `rh_subscription`

Config schema:

rh_subscription: (object)

username: (string) The username to use. Must be used with password. Should not be used with activation-key or org.

password: (string) The password to use. Must be used with username. Should not be used with activation-key or org.

activation-key: (string) The activation key to use. Must be used with org. Should not be used with username or password.

org: (integer) The organization number to use. Must be used with activation-key. Should not be used with username or password.

auto-attach: (boolean) Whether to attach subscriptions automatically.

service-level: (string) The service level to use when subscribing to RH repositories. auto-attach must be true for this to be used.

add-pool: (array of string) A list of pools ids add to the subscription.

enable-repo: (array of string) A list of repositories to enable.

disable-repo: (array of string) A list of repositories to disable.

rhsm-baseurl: (string) Sets the baseurl in `/etc/rhsm/rhsm.conf`.

server-hostname: (string) Sets the serverurl in `/etc/rhsm/rhsm.conf`.

Examples:

```
rh_subscription:
  username: joe@foo.bar
  ## Quote your password if it has symbols to be safe
  password: '1234abcd'

# --- Example2 ---
rh_subscription:
  activation-key: foobar
```

(continues on next page)

(continued from previous page)

```

    org: 12345

# --- Example3 ---
rh_subscription:
    activation-key: foobar
    org: 12345
    auto-attach: true
    service-level: self-support
    add-pool:
        - 1a1a1a1a1a1a1a1a1a1a1a1a1a1a1a1a
        - 2b2b2b2b2b2b2b2b2b2b2b2b2b2b2b2b
    enable-repo:
        - repo-id-to-enable
        - other-repo-id-to-enable
    disable-repo:
        - repo-id-to-disable
        - other-repo-id-to-disable
    # Alter the baseurl in /etc/rhsm/rhsm.conf
    rhsm-baseurl: http://url
    # Alter the server hostname in /etc/rhsm/rhsm.conf
    server-hostname: foo.bar.com

```

2.17.32 RightScale Userdata

Summary: Support rightscale configuration hooks

This module adds support for RightScale configuration hooks to cloud-init. RightScale adds an entry in the format `CLOUD_INIT_REMOTE_HOOK=http://...` to ec2 user-data. This module checks for this line in the raw userdata and retrieves any scripts linked by the RightScale user data and places them in the user scripts configuration directory, to be run later by `cc_scripts_user`.

Note: the `CLOUD_INIT_REMOTE_HOOK` config variable is present in the raw ec2 user data only, not in any cloud-config parts

Raw user data schema:

```
CLOUD_INIT_REMOTE_HOOK=<url>
```

Internal name: `cc_rightscale_userdata`

Module frequency: once-per-instance

Supported distros: all

2.17.33 Rsyslog

Summary: Configure system logging via rsyslog

This module configures remote system logging using rsyslog.

Configuration for remote servers can be specified in `configs`, but for convenience it can be specified as key value pairs in `remotes`.

Internal name: `cc_rsyslog`

Module frequency: once-per-instance

Supported distros: all

Activate only on keys: `rsyslog`

Config schema:

rsyslog: (object)

config_dir: (string) The directory where rsyslog configuration files will be written. Default: `/etc/rsyslog.d`.

config_filename: (string) The name of the rsyslog configuration file. Default: `20-cloud-config.conf`.

configs: (array of (string/object)) Each entry in `configs` is either a string or an object. Each config entry contains a configuration string and a file to write it to. For config entries that are an object, `filename` sets the target filename and `content` specifies the config string to write. For config entries that are only a string, the string is used as the config string to write. If the filename to write the config to is not specified, the value of the `config_filename` key is used. A file with the selected filename will be written inside the directory specified by `config_dir`.

Each object in `configs` list supports the following keys:

filename: (string)

content: (string)

remotes: (object) Each key is the name for an rsyslog remote entry. Each value holds the contents of the remote config for rsyslog. The config consists of the following parts:

- filter for log messages (defaults to `*.*`)
- optional leading `@` or `@@`, indicating udp and tcp respectively (defaults to `@`, for udp)
- ipv4 or ipv6 hostname or address. ipv6 addresses must be in `[::1]` format, (e.g. `@[fd00::1]:514`)
- optional port number (defaults to 514)

This module will provide sane defaults for any part of the remote entry that is not specified, so in most cases remote hosts can be specified just using `<name>: <address>`.

service_reload_command: (auto/array) The command to use to reload the rsyslog service after the config has been updated. If this is set to `auto`, then an appropriate command for the distro will be used. This is the default behavior. To manually set the command, use a list of command args (e.g. `[systemctl, restart, rsyslog]`).

Examples:

```
rsyslog:
  remotes:
    maas: 192.168.1.1
```

(continues on next page)

(continued from previous page)

```

    juju: 10.0.4.1
    service_reload_command: auto

# --- Example2 ---
rsyslog:
    config_dir: /opt/etc/rsyslog.d
    config_filename: 99-late-cloud-config.conf
    configs:
        - "*. * @@192.158.1.1"
        - content: "*. * @@192.0.2.1:10514"
          filename: 01-example.conf
        - content: |
            *. * @@syslogd.example.com
    remotes:
        maas: 192.168.1.1
        juju: 10.0.4.1
    service_reload_command: [your, syslog, restart, command]

```

2.17.34 Runcmd

Summary: Run arbitrary commands

Run arbitrary commands at a rc.local like time-frame with output to the console. Each item can be either a list or a string. The item type affects how it is executed:

- If the item is a string, it will be interpreted by `sh`.
- If the item is a list, the items will be executed as if passed to `execve(3)` (with the first arg as the command).

Note that the `runcmd` module only writes the script to be run later. The module that actually runs the script is `scripts-user` in the *Final* boot stage.

Note: all commands must be proper yaml, so you have to quote any characters yaml would eat (‘:’ can be problematic)

Note: when writing files, do not use `/tmp` dir as it races with `systemd-tmpfiles-clean` LP: #1707222. Use `/run/somedir` instead.

Internal name: `cc_runcmd`

Module frequency: once-per-instance

Supported distros: all

Activate only on keys: `runcmd`

Config schema:

runcmd: (array of (array of string/string/null))

Examples:

```

runcmd:
  - [ ls, -l, / ]
  - [ sh, -xc, "echo $(date) ': hello world!'" ]

```

(continues on next page)

(continued from previous page)

```
- [ sh, -c, echo "=====hello world'===== " ]
- ls -l /root
- [ wget, "http://example.org", -O, /tmp/index.html ]
```

2.17.35 Salt Minion

Summary: Setup and run salt minion

This module installs, configures and starts salt minion. If the `salt_minion` key is present in the config parts, then salt minion will be installed and started. Configuration for salt minion can be specified in the `conf` key under `salt_minion`. Any conf values present there will be assigned in `/etc/salt/minion`. The public and private keys to use for salt minion can be specified with `public_key` and `private_key` respectively. Optionally if you have a custom package name, service name or config directory you can specify them with `pkg_name`, `service_name` and `config_dir`.

Salt keys can be manually generated by: `salt-key --gen-keys=GEN_KEYS`, where `GEN_KEYS` is the name of the keypair, e.g. 'minion'. The keypair will be copied to `/etc/salt/pki` on the minion instance.

Internal name: `cc_salt_minion`

Module frequency: once-per-instance

Supported distros: all

Activate only on keys: `salt_minion`

Config schema:

salt_minion: (object)

pkg_name: (string) Package name to install. Default: `salt-minion`.

service_name: (string) Service name to enable. Default: `salt-minion`.

config_dir: (string) Directory to write config files to. Default: `/etc/salt`.

conf: (object) Configuration to be written to `config_dir/minion`.

grains: (object) Configuration to be written to `config_dir/grains`.

public_key: (string) Public key to be used by the salt minion.

private_key: (string) Private key to be used by salt minion.

pki_dir: (string) Directory to write key files. Default: `config_dir/pki/minion`.

Examples:

```
salt_minion:
  pkg_name: salt-minion
  service_name: salt-minion
  config_dir: /etc/salt
  conf:
    master: salt.example.com
  grains:
    role:
      - web
  public_key: |
    -----BEGIN PUBLIC KEY-----
    <key data>
    -----END PUBLIC KEY-----
```

(continues on next page)

(continued from previous page)

```
private_key: |
    -----BEGIN PRIVATE KEY-----
    <key data>
    -----END PRIVATE KEY-----
pki_dir: /etc/salt/pki/minion
```

2.17.36 Scripts Per Boot

Summary: Run per boot scripts

Any scripts in the `scripts/per-boot` directory on the datasource will be run every time the system boots. Scripts will be run in alphabetical order. This module does not accept any config keys.

Internal name: `cc_scripts_per_boot`

Module frequency: always

Supported distros: all

2.17.37 Scripts Per Instance

Summary: Run per instance scripts

Any scripts in the `scripts/per-instance` directory on the datasource will be run when a new instance is first booted. Scripts will be run in alphabetical order. This module does not accept any config keys.

Some cloud platforms change instance-id if a significant change was made to the system. As a result per-instance scripts will run again.

Internal name: `cc_scripts_per_instance`

Module frequency: once-per-instance

Supported distros: all

2.17.38 Scripts Per Once

Summary: Run one time scripts

Any scripts in the `scripts/per-once` directory on the datasource will be run only once. Changes to the instance will not force a re-run. The only way to re-run these scripts is to run the `clean` subcommand and reboot. Scripts will be run in alphabetical order. This module does not accept any config keys.

Internal name: `cc_scripts_per_once`

Module frequency: once

Supported distros: all

2.17.39 Scripts User

Summary: Run user scripts

This module runs all user scripts. User scripts are not specified in the `scripts` directory in the datasource, but rather are present in the `scripts` dir in the instance configuration. Any cloud-config parts with a `#!` will be treated as a script and run. Scripts specified as cloud-config parts will be run in the order they are specified in the configuration. This module does not accept any config keys.

Internal name: `cc_scripts_user`

Module frequency: once-per-instance

Supported distros: all

2.17.40 Scripts Vendor

Summary: Run vendor scripts

On select Datasources, vendors have a channel for the consumption of all supported user data types via a special channel called vendor data. Any scripts in the `scripts/vendor` directory in the datasource will be run when a new instance is first booted. Scripts will be run in alphabetical order. This module allows control over the execution of vendor data.

Internal name: `cc_scripts_vendor`

Module frequency: once-per-instance

Supported distros: all

Config schema:

vendor_data: (object)

enabled: (boolean) Whether vendor data is enabled or not. Default: `true`. DEPRECATED: Use of string for this value is DEPRECATED. Use a boolean value instead.

prefix: (string/array of (string/integer)) The command to run before any vendor scripts. Its primary use case is for profiling a script, not to prevent its run.

Examples:

```
vendor_data:
  enabled: true
  prefix: /usr/bin/ltrace

# --- Example2 ---
vendor_data:
  enabled: true
  prefix: [timeout, 30]

# --- Example3 ---
# Vendor data will not be processed
vendor_data:
  enabled: false
```

2.17.41 Seed Random

Summary: Provide random seed data

All cloud instances started from the same image will produce very similar data when they are first booted as they are all starting with the same seed for the kernel's entropy keyring. To avoid this, random seed data can be provided to the instance either as a string or by specifying a command to run to generate the data.

Configuration for this module is under the `random_seed` config key. If the cloud provides its own random seed data, it will be appended to data before it is written to `file`.

If the `command` key is specified, the given command will be executed. This will happen after `file` has been populated. That command's environment will contain the value of the `file` key as `RANDOM_SEED_FILE`. If a command is specified that cannot be run, no error will be reported unless `command_required` is set to `true`.

Internal name: `cc_seed_random`

Module frequency: once-per-instance

Supported distros: all

Config schema:

random_seed: (object)

file: (string) File to write random data to. Default: `/dev/urandom`.

data: (string) This data will be written to `file` before data from the `datasource`. When using a multiline value or specifying binary data, be sure to follow yaml syntax and use the `|` and `!binary` yaml format specifiers when appropriate.

encoding: (raw/base64/b64/gzip/gz) Used to decode data provided. Allowed values are `raw`, `base64`, `b64`, `gzip`, or `gz`. Default: `raw`.

command: (array of string) Execute this command to seed random. The command will have `RANDOM_SEED_FILE` in its environment set to the value of `file` above.

command_required: (boolean) If `true`, and `command` is not available to be run then an exception is raised and cloud-init will record failure. Otherwise, only debug error is mentioned. Default: `false`.

Examples:

```
random_seed:
  file: /dev/urandom
  data: my random string
  encoding: raw
  command: ['sh', '-c', 'dd if=/dev/urandom of=$RANDOM_SEED_FILE']
  command_required: true

# --- Example2 ---
# To use 'pollinate' to gather data from a remote entropy
# server and write it to '/dev/urandom', the following
# could be used:
random_seed:
  file: /dev/urandom
  command: ["pollinate", "--server=http://local.pollinate.server"]
  command_required: true
```

2.17.42 Set Hostname

Summary: Set hostname and FQDN

This module handles setting the system hostname and fully qualified domain name (FQDN). If `preserve_hostname` is set, then the hostname will not be altered.

A hostname and FQDN can be provided by specifying a full domain name under the `FQDN` key. Alternatively, a hostname can be specified using the `hostname` key, and the FQDN of the cloud will be used. If a FQDN specified with the `hostname` key, it will be handled properly, although it is better to use the `fqdn` config key. If both `fqdn` and `hostname` are set, the `prefer_fqdn_over_hostname` will force the use of FQDN in all distros when true, and when false it will force the short hostname. Otherwise, the hostname to use is distro-dependent.

Note: cloud-init performs no hostname input validation before sending the hostname to distro-specific tools, and most tools will not accept a trailing dot on the FQDN.

This module will run in the `init-local` stage before networking is configured if the hostname is set by metadata or user data on the local system.

This will occur on datasources like `nocloud` and `ovf` where metadata and user data are available locally. This ensures that the desired hostname is applied before any DHCP requests are performed on these platforms where dynamic DNS is based on initial hostname.

Internal name: `cc_set_hostname`

Module frequency: once-per-instance

Supported distros: all

Config schema:

preserve_hostname: (boolean) If true, the hostname will not be changed. Default: `false`.

hostname: (string) The hostname to set.

fqdn: (string) The fully qualified domain name to set.

prefer_fqdn_over_hostname: (boolean) If true, the `fqdn` will be used if it is set. If false, the hostname will be used. If unset, the result is distro-dependent.

Examples:

```
preserve_hostname: true
# --- Example2 ---
hostname: myhost
fqdn: myhost.example.com
prefer_fqdn_over_hostname: true
```

2.17.43 Set Passwords

Summary: Set user passwords and enable/disable SSH password auth

This module consumes three top-level config keys: `ssh_pwauth`, `chpasswd` and `password`.

The `ssh_pwauth` config key determines whether or not `sshd` will be configured to accept password authentication.

The `chpasswd` config key accepts a dictionary containing either or both of `users` and `expire`. The `users` key is used to assign a password to a corresponding pre-existing user. The `expire` key is used to set whether to expire all user passwords specified by this module, such that a password will need to be reset on the user's next login.

Note: Prior to cloud-init 22.3, the `expire` key only applies to plain text (including `RANDOM`) passwords. Post 22.3, the `expire` key applies to both plain text and hashed passwords.

`password` config key is used to set the default user's password. It is ignored if the `chpasswd` users is used. Note: the `list` keyword is deprecated in favor of `users`.

Internal name: `cc_set_passwords`

Module frequency: once-per-instance

Supported distros: all

Config schema:

ssh_pwauth: (boolean) Sets whether or not to accept password authentication. `true` will enable password auth. `false` will disable. Default is to leave the value unchanged. DEPRECATED: Use of non-boolean values for this field is DEPRECATED and will result in an error in a future version of cloud-init.

chpasswd: (object)

expire: (boolean) Whether to expire all user passwords such that a password will need to be reset on the user's next login. Default: `true`.

users: (array of object) Replaces the deprecated `list` key. This key represents a list of existing users to set passwords for. Each item under `users` contains the following required keys: `name` and `password` or in the case of a randomly generated password, `name` and `type`. The `type` key has a default value of `hash`, and may alternatively be set to `text` or `RANDOM`.

list: (string/array) DEPRECATED: List of `username:password` pairs. Each user will have the corresponding password set. A password can be randomly generated by specifying `RANDOM` or `R` as a user's password. A hashed password, created by a tool like `mkpasswd`, can be specified. A regex `(r'\$(1|2a|2y|5|6)(\$.+){2}')` is used to determine if a password value should be treated as a hash.

Use of a multiline string for this field is DEPRECATED and will result in an error in a future version of cloud-init.

password: (string) Set the default user's password. Ignored if `chpasswd list` is used.

Examples:

```
# Set a default password that would need to be changed
# at first login
ssh_pwauth: true
password: password1

# --- Example2 ---
# Disable ssh password authentication
# Don't require users to change their passwords on next login
# Set the password for user1 to be 'password1' (OS does hashing)
# Set the password for user2 to a pre-hashed password
# Set the password for user3 to be a randomly generated password,
# which will be written to the system console
ssh_pwauth: false
chpasswd:
  expire: false
  users:
    - name: user1
```

(continues on next page)

(continued from previous page)

```
password: password1
type: text
- name: user2
  password: $6$rounds=4096$5DJ8a9WMTEzIo5J4
  ↪ $Yms6imfeBvf3Yfu84mQBerh18l7OR1Wm1BJXZqFSpJ6BVas0AYJqIjP7czk0aAZHZi1kxQ5Y1IhgWN8K9NgxR1
  - name: user3
    type: RANDOM
```

2.17.44 Snap

Summary: Install, configure and manage snapd and snap packages

This module provides a simple configuration namespace in cloud-init to both setup snapd and install snaps.

Note: Both `assertions` and `commands` values can be either a dictionary or a list. If these configs are provided as a dictionary, the keys are only used to order the execution of the assertions or commands and the dictionary is merged with any vendor-data snap configuration provided. If a list is provided by the user instead of a dict, any vendor-data snap configuration is ignored.

The `assertions` configuration option is a dictionary or list of properly-signed snap assertions which will run before any snap commands. They will be added to snapd's assertion database by invoking `snap ack <aggregate_assertion_file>`.

`Snap commands` is a dictionary or list of individual snap commands to run on the target system. These commands can be used to create snap users, install snaps and provide snap configuration.

Note: If 'side-loading' private/unpublished snaps on an instance, it is best to create a snap seed directory and `seed.yaml` manifest in `/var/lib/snapd/seed/` which snapd automatically installs on startup.

Internal name: `cc_snap`

Module frequency: once-per-instance

Supported distros: ubuntu

Activate only on keys: `snap`

Config schema:

`snap:` (object)

assertions: (object/array of string) Properly-signed snap assertions which will run before and snap commands.

commands: (object/array of (string/array of string)) Snap commands to run on the target system.

Examples:

```
snap:
  assertions:
    00: |
      signed_assertion_blob_here
    02: |
      signed_assertion_blob_here
```

(continues on next page)

(continued from previous page)

```

commands:
  00: snap create-user --sudoer --known <snap-user>@mydomain.com
  01: snap install canonical-livepatch
  02: canonical-livepatch enable <AUTH_TOKEN>

# --- Example2 ---
# Convenience: the snap command can be omitted when specifying commands
# as a list and 'snap' will automatically be prepended.
# The following commands are equivalent:
snap:
  commands:
    00: ['install', 'vlc']
    01: ['snap', 'install', 'vlc']
    02: snap install vlc
    03: 'snap install vlc'

# --- Example3 ---
# You can use a list of commands
snap:
  commands:
    - ['install', 'vlc']
    - ['snap', 'install', 'vlc']
    - snap install vlc
    - 'snap install vlc'

# --- Example4 ---
# You can use a list of assertions
snap:
  assertions:
    - signed_assertion_blob_here
    - |
      signed_assertion_blob_here

```

2.17.45 Spacewalk

Summary: Install and configure spacewalk

This module installs spacewalk and applies basic configuration. If the `spacewalk` config key is present spacewalk will be installed. The server to connect to after installation must be provided in the `server` in spacewalk configuration. A proxy to connect through and a activation key may optionally be specified.

For more information about spacewalk see: <https://fedorahosted.org/spacewalk/>

Internal name: `cc_spacewalk`

Module frequency: once-per-instance

Supported distros: rhel, fedora

Activate only on keys: spacewalk

Config schema:

spacewalk: (object)

server: (string) The Spacewalk server to use.

proxy: (string) The proxy to use when connecting to Spacewalk.

activation_key: (string) The activation key to use when registering with Spacewalk.

Examples:

```
spacewalk:  
  server: <url>  
  proxy: <proxy host>  
  activation_key: <key>
```

2.17.46 SSH

Summary: Configure SSH and SSH keys

This module handles most configuration for SSH and both host and authorized SSH keys.

Authorized Keys

Authorized keys are a list of public SSH keys that are allowed to connect to a user account on a system. They are stored in `.ssh/authorized_keys` in that account's home directory. Authorized keys for the default user defined in `users` can be specified using `ssh_authorized_keys`. Keys should be specified as a list of public keys.

Note: see the `cc_set_passwords` module documentation to enable/disable SSH password authentication

Root login can be enabled/disabled using the `disable_root` config key. Root login options can be manually specified with `disable_root_opts`.

Supported public key types for the `ssh_authorized_keys` are:

- dsa
- rsa
- ecdsa
- ed25519
- [ecdsa-sha2-nistp256-cert-v01@openssh.com](#)
- ecdsa-sha2-nistp256
- [ecdsa-sha2-nistp384-cert-v01@openssh.com](#)
- ecdsa-sha2-nistp384
- [ecdsa-sha2-nistp521-cert-v01@openssh.com](#)
- ecdsa-sha2-nistp521
- [sk-ecdsa-sha2-nistp256-cert-v01@openssh.com](#)
- [sk-ecdsa-sha2-nistp256@openssh.com](#)
- [sk-ssh-ed25519-cert-v01@openssh.com](#)
- [sk-ssh-ed25519@openssh.com](#)
- [ssh-dss-cert-v01@openssh.com](#)
- ssh-dss

- `ssh-ed25519-cert-v01@openssh.com`
- `ssh-ed25519`
- `ssh-rsa-cert-v01@openssh.com`
- `ssh-rsa`
- `ssh-xmss-cert-v01@openssh.com`
- `ssh-xmss@openssh.com`

Note: this list has been filtered out from the supported keytypes of [OpenSSH](#) source, where the signonly keys are removed. Please see `ssh_util` for more information.

`dsa`, `rsa`, `ecdsa` and `ed25519` are added for legacy, as they are valid public keys in some old distros. They can possibly be removed in the future when support for the older distros are dropped

Host Keys

Host keys are for authenticating a specific instance. Many images have default host SSH keys, which can be removed using `ssh_deletekeys`.

Host keys can be added using the `ssh_keys` configuration key.

When host keys are generated the output of the `ssh-keygen` command(s) can be displayed on the console using the `ssh_quiet_keygen` configuration key.

Note: when specifying private host keys in `cloud-config`, care should be taken to ensure that the communication between the data source and the instance is secure

If no host keys are specified using `ssh_keys`, then keys will be generated using `ssh-keygen`. By default one public/private pair of each supported host key type will be generated. The key types to generate can be specified using the `ssh_genkeytypes` config flag, which accepts a list of host key types to use. For each host key type for which this module has been instructed to create a keypair, if a key of the same type is already present on the system (i.e. if `ssh_deletekeys` was false), no key will be generated.

Supported host key types for the `ssh_keys` and the `ssh_genkeytypes` config flags are:

- `dsa`
- `ecdsa`
- `ed25519`
- `rsa`

Unsupported host key types for the `ssh_keys` and the `ssh_genkeytypes` config flags are:

- `ecdsa-sk`
- `ed25519-sk`

Internal name: `cc_ssh`

Module frequency: once-per-instance

Supported distros: all

Config schema:

ssh_keys: (object) A dictionary entries for the public and private host keys of each desired key type. Entries in the `ssh_keys` config dict should have keys in the format `<key type>_private`, `<key type>_public`, and, optionally, `<key type>_certificate`, e.g. `rsa_private: <key>`, `rsa_public: <key>`, and `rsa_certificate: <key>`. Not all key types have to be specified, ones left unspecified will not be used. If this config option is used, then separate keys will not be automatically generated. In order to specify multiline private host keys and certificates, use yaml multiline syntax.

<key_type>: (string)

ssh_authorized_keys: (array of string) The SSH public keys to add `.ssh/authorized_keys` in the default user's home directory.

ssh_deletekeys: (boolean) Remove host SSH keys. This prevents re-use of a private host key from an image with default host SSH keys. Default: `true`.

ssh_genkeytypes: (array of string) The SSH key types to generate. Default: `[rsa, dsa, ecdsa, ed25519]`.

disable_root: (boolean) Disable root login. Default: `true`.

disable_root_opts: (string) Disable root login options. If `disable_root_opts` is specified and contains the string `$USER`, it will be replaced with the username of the default user. Default: `no-port-forwarding, no-agent-forwarding, no-X11-forwarding, command="echo 'Please login as the user \ "$USER\" rather than the user \"$DISABLE_USER\".';echo;sleep 10;exit 142"`.

allow_public_ssh_keys: (boolean) If `true`, will import the public SSH keys from the datasource's metadata to the user's `.ssh/authorized_keys` file. Default: `true`.

ssh_quiet_keygen: (boolean) If `true`, will suppress the output of key generation to the console. Default: `false`.

ssh_publish_hostkeys: (object)

enabled: (boolean) If `true`, will read host keys from `/etc/ssh/*.pub` and publish them to the data-source (if supported). Default: `true`.

blacklist: (array of string) The SSH key types to ignore when publishing. Default: `[dsa]`.

Examples:

```
ssh_keys:
  rsa_private: |
    -----BEGIN RSA PRIVATE KEY-----
    MIIBxwIBAAJhAKD0YSHy73nUgysO13XsJmd4fHiFyQ+00R7VVu2iV9Qco
    ...
    -----END RSA PRIVATE KEY-----
  rsa_public: ssh-rsa AAAAB3NzaC1yc2EAAAABIwAAAGEAoPRhIfLvedSDKw7Xd ...
  rsa_certificate: |
    ssh-rsa-cert-v01@openssh.com AAAAIHNzaC1lZDI1NTE5LWNlcnQt ...
  dsa_private: |
    -----BEGIN DSA PRIVATE KEY-----
    MIIBxwIBAAJhAKD0YSHy73nUgysO13XsJmd4fHiFyQ+00R7VVu2iV9Qco
    ...
    -----END DSA PRIVATE KEY-----
  dsa_public: ssh-dsa AAAAB3NzaC1yc2EAAAABIwAAAGEAoPRhIfLvedSDKw7Xd ...
  dsa_certificate: |
    ssh-dsa-cert-v01@openssh.com AAAAIHNzaC1lZDI1NTE5LWNlcnQt ...
ssh_authorized_keys:
- ssh-rsa AAAAB3NzaC1yc2EAAAABIwAAAGEA3FSyQwBI6Z+nCSjUU ...
- ssh-rsa AAAAB3NzaC1yc2EAAAABIwAAAEQA3I7VUf2l5gSn5uavROsc5HRDpZ ...
```

(continues on next page)

(continued from previous page)

```
ssh_deletekeys: true
ssh_genkeytypes: [rsa, dsa, ecdsa, ed25519]
disable_root: true
disable_root_opts: no-port-forwarding,no-agent-forwarding,no-X11-forwarding
allow_public_ssh_keys: true
ssh_quiet_keygen: true
ssh_publish_hostkeys:
  enabled: true
  blacklist: [dsa]
```

2.17.47 SSH AuthKey Fingerprints

Summary: Log fingerprints of user SSH keys

Write fingerprints of authorized keys for each user to log. This is enabled by default, but can be disabled using `no_ssh_fingerprints`. The hash type for the keys can be specified, but defaults to `sha256`.

Internal name: `cc_ssh_authkey_fingerprints`

Module frequency: once-per-instance

Supported distros: all

Config schema:

`no_ssh_fingerprints`: (boolean) If true, SSH fingerprints will not be written. Default: `false`.

`authkey_hash`: (string) The hash type to use when generating SSH fingerprints. Default: `sha256`.

Examples:

```
no_ssh_fingerprints: true
# --- Example2 ---
authkey_hash: sha512
```

2.17.48 SSH Import ID

Summary: Import SSH id

This module imports SSH keys from either a public keyserver, usually `launchpad` or `github` using `ssh-import-id`. Keys are referenced by the username they are associated with on the keyserver. The keyserver can be specified by prepending either `lp:` for `launchpad` or `gh:` for `github` to the username.

Internal name: `cc_ssh_import_id`

Module frequency: once-per-instance

Supported distros: `ubuntu`, `debian`, `cos`

Config schema:

`ssh_import_id`: (array of string)

Examples:

```
ssh_import_id:
  - user
```

(continues on next page)

(continued from previous page)

- gh:user
- lp:user

2.17.49 Timezone

Summary: Set the system timezone

Sets the system timezone based on the value provided.

Internal name: cc_timezone

Module frequency: once-per-instance

Supported distros: all

Activate only on keys: timezone

Config schema:

timezone: (string) The timezone to use as represented in /usr/share/zoneinfo.

Examples:

timezone: US/Eastern

2.17.50 Ubuntu Advantage

Summary: Configure Ubuntu Advantage support services

Attach machine to an existing Ubuntu Advantage support contract and enable or disable support services such as Livepatch, ESM, FIPS and FIPS Updates. When attaching a machine to Ubuntu Advantage, one can also specify services to enable. When the 'enable' list is present, only named services will be activated. Whereas if the 'enable' list is not present, the contract's default services will be enabled.

On Pro instances, when ubuntu_advantage config is provided to cloud-init, Pro's auto-attach feature will be disabled and cloud-init will perform the Pro auto-attach ignoring the token key. The enable and enable_beta values will strictly determine what services will be enabled, ignoring contract defaults.

Note that when enabling FIPS or FIPS updates you will need to schedule a reboot to ensure the machine is running the FIPS-compliant kernel. See [Power State Change](#) for information on how to configure cloud-init to perform this reboot.

Internal name: cc_ubuntu_advantage

Module frequency: once-per-instance

Supported distros: ubuntu

Activate only on keys: ubuntu_advantage, ubuntu-advantage

Config schema:

ubuntu_advantage: (object)

enable: (array of string) Optional list of ubuntu-advantage services to enable. Any of: cc-eal, cis, esm-infra, fips, fips-updates, livepatch. By default, a given contract token will automatically enable a number of services, use this list to supplement which services should additionally be enabled. Any service unavailable on a given Ubuntu release or unentitled in a given contract will remain disabled. In Ubuntu Pro instances, if this list is given, then only those services will be enabled, ignoring contract defaults. Passing beta services here will cause an error.

enable_beta: (array of string) Optional list of ubuntu-advantage beta services to enable. By default, a given contract token will automatically enable a number of services, use this list to supplement which services should additionally be enabled. Any service unavailable on a given Ubuntu release or unentitled in a given contract will remain disabled. In Ubuntu Pro instances, if this list is given, then only those services will be enabled, ignoring contract defaults.

token: (string) Contract token obtained from <https://ubuntu.com/advantage> to attach. Required for non-Pro instances.

features: (object) Ubuntu Advantage features.

disable_auto_attach: (boolean) Optional boolean for controlling if ua-auto-attach.service (in Ubuntu Pro instances) will be attempted each boot. Default: `false`.

config: (object) Configuration settings or override Ubuntu Advantage config.

http_proxy: (string/null) Ubuntu Advantage HTTP Proxy URL or null to unset.

https_proxy: (string/null) Ubuntu Advantage HTTPS Proxy URL or null to unset.

global_apt_http_proxy: (string/null) HTTP Proxy URL used for all APT repositories on a system or null to unset. Stored at `/etc/apt/apt.conf.d/90ubuntu-advantage-aptproxy`.

global_apt_https_proxy: (string/null) HTTPS Proxy URL used for all APT repositories on a system or null to unset. Stored at `/etc/apt/apt.conf.d/90ubuntu-advantage-aptproxy`.

ua_apt_http_proxy: (string/null) HTTP Proxy URL used only for Ubuntu Advantage APT repositories or null to unset. Stored at `/etc/apt/apt.conf.d/90ubuntu-advantage-aptproxy`.

ua_apt_https_proxy: (string/null) HTTPS Proxy URL used only for Ubuntu Advantage APT repositories or null to unset. Stored at `/etc/apt/apt.conf.d/90ubuntu-advantage-aptproxy`.

Examples:

```
# Attach the machine to an Ubuntu Advantage support contract with a
# UA contract token obtained from https://ubuntu.com/advantage.
ubuntu_advantage:
  token: <ua_contract_token>

# --- Example2 ---
# Attach the machine to an Ubuntu Advantage support contract enabling
# only fips and esm services. Services will only be enabled if
# the environment supports said service. Otherwise warnings will
# be logged for incompatible services specified.
ubuntu_advantage:
  token: <ua_contract_token>
  enable:
    - fips
    - esm

# --- Example3 ---
# Attach the machine to an Ubuntu Advantage support contract and enable
# the FIPS service. Perform a reboot once cloud-init has
# completed.
power_state:
```

(continues on next page)

(continued from previous page)

```

mode: reboot
ubuntu_advantage:
  token: <ua_contract_token>
  enable:
    - fips

# --- Example4 ---
# Set a http(s) proxy before attaching the machine to an
# Ubuntu Advantage support contract and enabling the FIPS service.
ubuntu_advantage:
  token: <ua_contract_token>
  config:
    http_proxy: 'http://some-proxy:8088'
    https_proxy: 'https://some-proxy:8088'
    global_apt_https_proxy: 'https://some-global-apt-proxy:8088/'
    global_apt_http_proxy: 'http://some-global-apt-proxy:8088/'
    ua_apt_http_proxy: 'http://10.0.10.10:3128'
    ua_apt_https_proxy: 'https://10.0.10.10:3128'
  enable:
    - fips

# --- Example5 ---
# On Ubuntu PRO instances, auto-attach but enable no PRO services.
ubuntu_advantage:
  enable: []
  enable_beta: []

# --- Example6 ---
# Enable esm and beta realtime-kernel services in Ubuntu Pro instances.
ubuntu_advantage:
  enable:
    - esm
  enable_beta:
    - realtime-kernel

# --- Example7 ---
# Disable auto-attach in Ubuntu Pro instances.
ubuntu_advantage:
  features:
    disable_auto_attach: True

```

2.17.51 Ubuntu Autoinstall

Summary: Support Ubuntu live-server install syntax

Ubuntu’s autoinstall YAML supports single-system automated installs in either the live-server install, via the subiquity snap, or the next generation desktop installer, via *ubuntu-desktop-install* snap. When “autoinstall” directives are provided in either #cloud-config user-data or /etc/cloud/cloud.cfg.d validate minimal autoinstall schema adherence and emit a warning if the live-installer is not present.

The live-installer will use autoinstall directives to seed answers to configuration prompts during system install to allow for a “touchless” or non-interactive Ubuntu system install.

For more details on Ubuntu’s autoinstaller:

<https://ubuntu.com/server/docs/install/autoinstall>

Internal name: cc_ubuntu_autoinstall

Module frequency: once

Supported distros: ubuntu

Activate only on keys: autoinstall

Config schema:

autoinstall: (object) Opaque autoinstall schema definition for Ubuntu autoinstall. Full schema processed by live-installer. See: <https://ubuntu.com/server/docs/install/autoinstall-reference>.

version: (integer)

Examples:

```
# Tell the live-server installer to provide dhcp6 network config
# and LVM on a disk matching the serial number prefix CT
autoinstall:
  version: 1
  network:
    version: 2
    ethernets:
      enp0s31f6:
        dhcp6: yes
  storage:
    layout:
      name: lvm
      match:
        serial: CT*
```

2.17.52 Ubuntu Drivers

Summary: Interact with third party drivers in Ubuntu.

This module interacts with the ‘ubuntu-drivers’ command to install third party driver packages.

Internal name: cc_ubuntu_drivers

Module frequency: once-per-instance

Supported distros: ubuntu

Activate only on keys: drivers

Config schema:

drivers: (object)

nvidia: (object)

license-accepted: (boolean) Do you accept the NVIDIA driver license?.

version: (string) The version of the driver to install (e.g. “390”, “410”). Defaults to the latest version.

Examples:

```
drivers:
  nvidia:
    license-accepted: true
```

2.17.53 Update Etc Hosts

Summary: Update the hosts file (usually `/etc/hosts`)

This module will update the contents of the local hosts database (hosts file; usually `/etc/hosts`) based on the host-name/fqdn specified in config. Management of the hosts file is controlled using `manage_etc_hosts`. If this is set to false, cloud-init will not manage the hosts file at all. This is the default behavior.

If set to true, cloud-init will generate the hosts file using the template located in `/etc/cloud/templates/hosts.tpl`. In the `/etc/cloud/templates/hosts.tpl` template, the strings `$hostname` and `$fqdn` will be replaced with the hostname and fqdn respectively.

If `manage_etc_hosts` is set to `localhost`, then cloud-init will not rewrite the hosts file entirely, but rather will ensure that a entry for the fqdn with a distribution dependent ip is present (i.e. `ping <hostname>` will ping `127.0.0.1` or `127.0.1.1` or other ip).

Note: if `manage_etc_hosts` is set true, the contents of the hosts file will be updated every boot. To make any changes to the hosts file persistent they must be made in `/etc/cloud/templates/hosts.tpl`

Note: for instructions on specifying hostname and fqdn, see documentation for `cc_set_hostname`

Internal name: `cc_update_etc_hosts`

Module frequency: always

Supported distros: all

Activate only on keys: `manage_etc_hosts`

Config schema:

manage_etc_hosts: (true/false/localhost) Whether to manage `/etc/hosts` on the system. If true, render the hosts file using `/etc/cloud/templates/hosts.tpl` replacing `$hostname` and `$fqdn`. If localhost, append a `127.0.1.1` entry that resolves from FQDN and hostname every boot. Default: false. DEPRECATED: Value template will be dropped after April 2027. Use true instead.

fqdn: (string) Optional fully qualified domain name to use when updating `/etc/hosts`. Preferred over hostname if both are provided. In absence of hostname and fqdn in cloud-config, the local-hostname value will be used from datasource metadata.

hostname: (string) Hostname to set when rendering `/etc/hosts`. If fqdn is set, the hostname extracted from fqdn overrides hostname.

Examples:

```
# Do not update or manage /etc/hosts at all. This is the default behavior.
#
# Whatever is present at instance boot time will be present after boot.
# User changes will not be overwritten.
manage_etc_hosts: false
```

(continues on next page)

(continued from previous page)

```
# --- Example2 ---
# Manage /etc/hosts with cloud-init.
# On every boot, /etc/hosts will be re-written from
# ``/etc/cloud/templates/hosts.tpl``.
#
# The strings '$hostname' and '$fqdn' are replaced in the template
# with the appropriate values either from the config-config ``fqdn`` or
# ``hostname`` if provided. When absent, the cloud metadata will be
# checked for ``local-hostname`` which can be split into <hostname>.<fqdn>.
#
# To make modifications persistent across a reboot, you must modify
# ``/etc/cloud/templates/hosts.tpl``.
manage_etc_hosts: true

# --- Example3 ---
# Update /etc/hosts every boot providing a "localhost" 127.0.1.1 entry
# with the latest hostname and fqdn as provided by either IMDS or
# cloud-config.
# All other entries will be left as is.
# 'ping `hostname`' will ping 127.0.1.1
manage_etc_hosts: localhost
```

2.17.54 Update Hostname

Summary: Update hostname and fqdn

This module will update the system hostname and fqdn. If `preserve_hostname` is set `true`, then the hostname will not be altered.

Note: for instructions on specifying hostname and fqdn, see documentation for `cc_set_hostname`

Internal name: `cc_update_hostname`

Module frequency: always

Supported distros: all

Config schema:

preserve_hostname: (boolean) Do not update system hostname when true. Default: false.

prefer_fqdn_over_hostname: (boolean) By default, it is distro-dependent whether cloud-init uses the short hostname or fully qualified domain name when both `local-hostname` and `fqdn` are both present in instance metadata. When set `true`, use fully qualified domain name if present as hostname instead of short hostname. When set `false`, use hostname config value if present, otherwise fallback to `fqdn`.

Examples:

```
# By default: when ``preserve_hostname`` is not specified cloud-init
# updates ``/etc/hostname`` per-boot based on the cloud provided
# ``local-hostname`` setting. If you manually change ``/etc/hostname``
# after boot cloud-init will no longer modify it.
#
# This default cloud-init behavior is equivalent to this cloud-config:
```

(continues on next page)

(continued from previous page)

```
preserve_hostname: false

# --- Example2 ---
# Prevent cloud-init from updating the system hostname.
preserve_hostname: true

# --- Example3 ---
# Prevent cloud-init from updating ``/etc/hostname``
preserve_hostname: true

# --- Example4 ---
# Set hostname to "external.fqdn.me" instead of "myhost"
fqdn: external.fqdn.me
hostname: myhost
prefer_fqdn_over_hostname: true

# --- Example5 ---
# Set hostname to "external" instead of "external.fqdn.me" when
# cloud metadata provides the ``local-hostname``: "external.fqdn.me".
prefer_fqdn_over_hostname: false
```

2.17.55 Users and Groups

Summary: Configure users and groups

This module configures users and groups. For more detailed information on user options, see the *Including users and groups* config example.

Groups to add to the system can be specified under the `groups` key as a string of comma-separated groups to create, or a list. Each item in the list should either contain a string of a single group to create, or a dictionary with the group name as the key and string of a single user as a member of that group or a list of users who should be members of the group.

Note: Groups are added before users, so any users in a group list must already exist on the system.

Users to add can be specified as a string or list under the `users` key. Each entry in the list should either be a string or a dictionary. If a string is specified, that string can be comma-separated usernames to create or the reserved string `default` which represents the primary admin user used to access the system. The `default` user varies per distribution and is generally configured in `/etc/cloud/cloud.cfg` by the `default_user` key.

Each `users` dictionary item must contain either a `name` or `snapuser` key, otherwise it will be ignored. Omission of `default` as the first item in the `users` list skips creation the default user. If no `users` key is provided the default behavior is to create the default user via this config:

```
users:
- default
```

Note: Specifying a hash of a user's password with `passwd` is a security risk if the cloud-config can be intercepted. SSH authentication is preferred.

Note: If specifying a sudo rule for a user, ensure that the syntax for the rule is valid, as it is not checked by cloud-init.

Note: Most of these configuration options will not be honored if the user already exists. The following options are the exceptions; they are applied to already-existing users: `plain_text_passwd`, `hashed_passwd`, `lock_passwd`, `sudo`, `ssh_authorized_keys`, `ssh_redirect_user`.

The `user` key can be used to override the `default_user` configuration defined in `/etc/cloud/cloud.cfg`. The `user` value should be a dictionary which supports the same config keys as the `users` dictionary items.

Internal name: `cc_users_groups`

Module frequency: once-per-instance

Supported distros: all

Config schema:

groups: (string/object/array of (string/object))

Each object in **groups** list supports the following keys:

<group_name>: (string/array of string) Optional string of single username or a list of usernames to add to the group.

user: (string/object) The `user` dictionary values override the `default_user` configuration from `/etc/cloud/cloud.cfg`. The `user` dictionary keys supported for the `default_user` are the same as the `users` schema.

users: (string/object/array of (string/array of string/object))

Each object in **users** list supports the following keys:

name: (string) The user's login name. Required otherwise user creation will be skipped for this user.

expiredate: (string) Optional. Date on which the user's account will be disabled. Default: `null`.

gecos: (string) Optional comment about the user, usually a comma-separated string of real name and contact information.

groups: (string/object/array) Optional comma-separated string of groups to add the user to.

homedir: (string) Optional home dir for user. Default: `/home/<username>`.

inactive: (string) Optional string representing the number of days until the user is disabled.

.

lock_passwd: (boolean) DEPRECATED: Dropped after April 2027. Use `lock_passwd`. Default: `true`.

lock_passwd: (boolean) Disable password login. Default: `true`.

no_create_home: (boolean) Do not create home directory. Default: `false`.

no_log_init: (boolean) Do not initialize lastlog and faillog for user. Default: `false`.

no_user_group: (boolean) Do not create group named after user. Default: `false`.

passwd: (string) Hash of user password applied when user does not exist. This will NOT be applied if the user already exists. To generate this hash, run: `mkpasswd --method=SHA-512`

`--rounds=4096`. **Note:** While hashed password is better than plain text, using `passwd` in user-data represents a security risk as user-data could be accessible by third-parties depending on your cloud platform.

hashed_passwd: (string) Hash of user password to be applied. This will be applied even if the user is pre-existing. To generate this hash, run: `mkpasswd --method=SHA-512 --rounds=4096`. **Note:** While `hashed_password` is better than `plain_text_passwd`, using `passwd` in user-data represents a security risk as user-data could be accessible by third-parties depending on your cloud platform.

plain_text_passwd: (string) Clear text of user password to be applied. This will be applied even if the user is pre-existing. There are many more secure options than using plain text passwords, such as `ssh_import_id` or `hashed_passwd`. Do not use this in production as user-data and your password can be exposed.

create_groups: (boolean) Boolean set `false` to disable creation of specified user groups. Default: `true`.

primary_group: (string) Primary group for user. Default: `<username>`.

selinux_user: (string) SELinux user for user's login. Default to default SELinux user.

shell: (string) Path to the user's login shell. The default is to set no shell, which results in a system-specific default being used.

snapuser: (string) Specify an email address to create the user as a Snappy user through `snap create-user`. If an Ubuntu SSO account is associated with the address, username and SSH keys will be requested from there.

ssh_authorized_keys: (array of string) List of SSH keys to add to user's authkeys file. Can not be combined with `ssh_redirect_user`.

ssh_import_id: (array of string) List of SSH IDs to import for user. Can not be combined with `ssh_redirect_user`.

ssh_redirect_user: (boolean) Boolean set to `true` to disable SSH logins for this user. When specified, all cloud meta-data public SSH keys will be set up in a disabled state for this username. Any SSH login as this username will timeout and prompt with a message to login instead as the `default_username` for this instance. Default: `false`. This key can not be combined with `ssh_import_id` or `ssh_authorized_keys`.

system: (boolean) Optional. Create user as system user with no home directory. Default: `false`.

sudo: (string/null) Sudo rule to use or `false`. Absence of a sudo value or `null` will result in no sudo rules added for this user. DEPRECATED: The value `false` will be dropped after April 2027. Use `null` or no sudo key instead.

uid: (integer) The user's ID. Default is next available value. DEPRECATED: The use of string type will be dropped after April 2027. Use an integer instead.

Examples:

```
# Add the ``default_user`` from /etc/cloud/cloud.cfg.
# This is also the default behavior of cloud-init when no `users` key
# is provided.
users:
- default

# --- Example2 ---
```

(continues on next page)

(continued from previous page)

```

# Add the 'admingroup' with members 'root' and 'sys' and an empty
# group cloud-users.
groups:
- admingroup: [root,sys]
- cloud-users

# --- Example3 ---
# Skip creation of the <default> user and only create newsuper.
# Password-based login is rejected, but the github user TheRealFalcon
# and the launchpad user falcojr can SSH as newsuper. The default
# shell for newsuper is bash instead of system default.
users:
- name: newsuper
  geccos: Big Stuff
  groups: users, admin
  sudo: ALL=(ALL) NOPASSWD:ALL
  shell: /bin/bash
  lock_passwd: true
  ssh_import_id:
    - lp:falcojr
    - gh:TheRealFalcon

# --- Example4 ---
# On a system with SELinux enabled, add youruser and set the
# SELinux user to 'staff_u'. When omitted on SELinux, the system will
# select the configured default SELinux user.
users:
- default
- name: youruser
  selinux_user: staff_u

# --- Example5 ---
# To redirect a legacy username to the <default> user for a
# distribution, ssh_redirect_user will accept an SSH connection and
# emit a message telling the client to ssh as the <default> user.
# SSH clients will get the message:
users:
- default
- name: nosshlogins
  ssh_redirect_user: true

# --- Example6 ---
# Override any ``default_user`` config in /etc/cloud/cloud.cfg with
# supplemental config options.
# This config will make the default user to mynewdefault and change
# the user to not have sudo rights.
ssh_import_id: [chad.smith]
user:
  name: mynewdefault
  sudo: null

```

2.17.56 Wireguard

Summary: Module to configure Wireguard tunnel

Wireguard module provides a dynamic interface for configuring Wireguard (as a peer or server) in an easy way.

This module takes care of:

- writing interface configuration files
- enabling and starting interfaces
- installing wireguard-tools package
- loading wireguard kernel module
- executing readiness probes

What's a readiness probe?

The idea behind readiness probes is to ensure Wireguard connectivity before continuing the cloud-init process. This could be useful if you need access to specific services like an internal APT Repository Server (e.g Landscape) to install/update packages.

Example:

An edge device can't access the internet but uses cloud-init modules which will install packages (e.g landscape, packages, ubuntu_advantage). Those modules will fail due to missing internet connection. The "wireguard" module fixes that problem as it waits until all readinessprobes (which can be arbitrary commands - e.g. checking if a proxy server is reachable over Wireguard network) are finished before continuing the cloud-init "config" stage.

Note: In order to use DNS with Wireguard you have to install `resolvconf` package or symlink it to `systemd's resolvectl`, otherwise `wg-quick` commands will throw an error message that executable `resolvconf` is missing which leads wireguard module to fail.

Internal name: `cc_wireguard`

Module frequency: once-per-instance

Supported distros: ubuntu

Activate only on keys: wireguard

Config schema:

wireguard: (null/object)

interfaces: (array of object)

Each object in **interfaces** list supports the following keys:

name: (string) Name of the interface. Typically `wgx` (example: `wg0`).

config_path: (string) Path to configuration file of Wireguard interface.

content: (string) Wireguard interface configuration. Contains key, peer, .

readinessprobe: (array of string) List of shell commands to be executed as probes.

Examples:

```
# Configure one or more WG interfaces and provide optional readinessprobes
wireguard:
  interfaces:
```

(continues on next page)

(continued from previous page)

```

- name: wg0
  config_path: /etc/wireguard/wg0.conf
  content: |
    [Interface]
    PrivateKey = <private_key>
    Address = <address>
    [Peer]
    PublicKey = <public_key>
    Endpoint = <endpoint_ip>:<endpoint_ip_port>
    AllowedIPs = <allowedip1>, <allowedip2>, ...
- name: wg1
  config_path: /etc/wireguard/wg1.conf
  content: |
    [Interface]
    PrivateKey = <private_key>
    Address = <address>
    [Peer]
    PublicKey = <public_key>
    Endpoint = <endpoint_ip>:<endpoint_ip_port>
    AllowedIPs = <allowedip1>
  readinessprobe:
    - 'systemctl restart service'
    - 'curl https://webhook.endpoint/example'
    - 'nc -zv some-service-fqdn 443'

```

2.17.57 Write Files

Summary: write arbitrary files

Write out arbitrary content to files, optionally setting permissions. Parent folders in the path are created if absent. Content can be specified in plain text or binary. Data encoded with either base64 or binary gzip data can be specified and will be decoded before being written. For empty file creation, content can be omitted.

Note: if multiline data is provided, care should be taken to ensure that it follows yaml formatting standards. to specify binary data, use the yaml option `!!binary`

Note: Do not write files under `/tmp` during boot because of a race with `systemd-tmpfiles-clean` that can cause temp files to get cleaned during the early boot process. Use `/run/somedir` instead to avoid race LP:1707222.

Internal name: `cc_write_files`

Module frequency: once-per-instance

Supported distros: all

Activate only on keys: `write_files`

Config schema:

write_files: (array of object)

Each object in **write_files** list supports the following keys:

path: (string) Path of the file to which **content** is decoded and written.

content: (string) Optional content to write to the provided **path**. When content is present and encoding is not 'text/plain', decode the content prior to writing. Default: ''.

owner: (string) Optional owner:group to chown on the file. Default: root:root.

permissions: (string) Optional file permissions to set on **path** represented as an octal string '0###'. Default: 0o644.

encoding: (gz/gzip/gz+base64/gzip+base64/gz+b64/gzip+b64/b64/base64/text/plain) Optional encoding type of the content. Default is text/plain and no content decoding is performed. Supported encoding types are: gz, gzip, gz+base64, gzip+base64, gz+b64, gzip+b64, b64, base64.

append: (boolean) Whether to append content to existing file if **path** exists. Default: false.

defer: (boolean) Defer writing the file until 'final' stage, after users were created, and packages were installed. Default: false.

Examples:

```
# Write out base64 encoded content to /etc/sysconfig/selinux
write_files:
- encoding: b64
  content: CiMgVGhpcyBmaWxlIGNvbnRyb2xzIHRob2ZSBzdGF0ZSBvZiBTRUxpbnV4...
  owner: root:root
  path: /etc/sysconfig/selinux
  permissions: '0644'

# --- Example2 ---
# Appending content to an existing file
write_files:
- content: |
    15 * * * * root ship_logs
  path: /etc/crontab
  append: true

# --- Example3 ---
# Provide gzipped binary content
write_files:
- encoding: gzip
  content: !!binary |
    H4sIAIDb/U8C/1NW1E/KzNMvzuBKTc7IV8hIzcnJVyJPL8pJ4QIA6N+MVxsAAAA=
  path: /usr/bin/hello
  permissions: '0755'

# --- Example4 ---
# Create an empty file on the system
write_files:
- path: /root/CLOUD_INIT_WAS_HERE

# --- Example5 ---
# Defer writing the file until after the package (Nginx) is
# installed and its user is created alongside
write_files:
```

(continues on next page)

(continued from previous page)

```
- path: /etc/nginx/conf.d/example.com.conf
  content: |
    server {
      server_name example.com;
      listen 80;
      root /var/www;
      location / {
        try_files $uri $uri/ $uri.html =404;
      }
    }
  owner: 'nginx:nginx'
  permissions: '0640'
  defer: true
```

2.17.58 Yum Add Repo

Summary: Add yum repository configuration to the system

Add yum repository configuration to `/etc/yum.repos.d`. Configuration files are named based on the opaque dictionary key under the `yum_repos` they are specified with. If a config file already exists with the same name as a config entry, the config entry will be skipped.

Internal name: `cc_yum_add_repo`

Module frequency: once-per-instance

Supported distros: almalinux, centos, cloudlinux, eurolinux, fedora, mariner, openEuler, openmandriva, photon, rhel, rocky, virtuozone

Activate only on keys: `yum_repos`

Config schema:

yum_repo_dir: (string) The repo parts directory where individual yum repo config files will be written. Default: `/etc/yum.repos.d`.

yum_repos: (object)

<repo_name>: (object) Object keyed on unique yum repo IDs. The key used will be used to write yum repo config files in `yum_repo_dir/<repo_key_id>.repo`.

baseurl: (string) URL to the directory where the yum repository's 'repodata' directory lives.

name: (string) Optional human-readable name of the yum repo.

enabled: (boolean) Whether to enable the repo. Default: `true`.

<yum_config_option>: (integer/boolean/string) Any supported yum repository configuration options will be written to the yum repo config file. See: `man yum.conf`.

Examples:

```
yum_repos:
  my_repo:
    baseurl: http://blah.org/pub/epel/testing/5/$basearch/
yum_repo_dir: /store/custom/yum.repos.d

# --- Example2 ---
```

(continues on next page)

(continued from previous page)

```

# Enable cloud-init upstream's daily testing repo for EPEL 8 to
# install latest cloud-init from tip of `main` for testing.
yum_repos:
  cloud-init-daily:
    name: Copr repo for cloud-init-dev owned by @cloud-init
    baseurl: https://download.copr.fedorainfracloud.org/results/@cloud-init/cloud-init-
↳ dev/epel-8-$basearch/
    type: rpm-md
    skip_if_unavailable: true
    gpgcheck: true
    gpgkey: https://download.copr.fedorainfracloud.org/results/@cloud-init/cloud-init-
↳ dev/pubkey.gpg
    enabled_metadata: 1

# --- Example3 ---
# Add the file /etc/yum.repos.d/epel_testing.repo which can then
# subsequently be used by yum for later operations.
yum_repos:
# The name of the repository
  epel-testing:
    baseurl: https://download.copr.fedorainfracloud.org/results/@cloud-init/cloud-init-
↳ dev/pubkey.gpg
    enabled: false
    failovermethod: priority
    gpgcheck: true
    gpgkey: file:///etc/pki/rpm-gpg/RPM-GPG-KEY-EPEL
    name: Extra Packages for Enterprise Linux 5 - Testing

# --- Example4 ---
# Any yum repo configuration can be passed directly into
# the repository file created. See: man yum.conf for supported
# config keys.
#
# Write /etc/yum.conf.d/my-package-stream.repo with gpgkey checks
# on the repo data of the repository enabled.
yum_repos:
  my package stream:
    baseurl: http://blah.org/pub/epel/testing/5/$basearch/
    mirrorlist: http://some-url-to-list-of-baseurls
    repo_gpgcheck: 1
    enable_gpgcheck: true
    gpgkey: https://url.to.ascii-armored-gpg-key

```

2.17.59 Zypper Add Repo

Summary: Configure zypper behavior and add zypper repositories

Zypper behavior can be configured using the `config` key, which will modify `/etc/zypp/zypp.conf`. The configuration writer will only append the provided configuration options to the configuration file. Any duplicate options will be resolved by the way the `zypp.conf` INI file is parsed.

Note: Setting `configdir` is not supported and will be skipped.

The `repos` key may be used to add repositories to the system. Beyond the required `id` and `baseurl` attributions, no validation is performed on the `repos` entries. It is assumed the user is familiar with the zypper repository file format.

Internal name: `cc_zypper_add_repo`

Module frequency: always

Supported distros: opensuse, sles

Activate only on keys: zypper

Config schema:

zypper: (object)

repos: (array of object)

Each object in **repos** list supports the following keys:

id: (string) The unique id of the repo, used when writing `/etc/zypp/repos.d/<id>.repo`.

baseurl: (string) The base repository URL.

config: (object) Any supported `zypp.conf` key is written to `/etc/zypp/zypp.conf`.

Examples:

```
zypper:
  repos:
    - id: opensuse-oss
      name: os-oss
      baseurl: http://dl.opensuse.org/dist/leap/v/repo/oss/
      enabled: 1
      autorefresh: 1
    - id: opensuse-oss-update
      name: os-oss-up
      baseurl: http://dl.opensuse.org/dist/leap/v/update
      # any setting per
      # https://en.opensuse.org/openSUSE:Standards_RepoInfo
      # enable and autorefresh are on by default
  config:
    reposdir: /etc/zypp/repos.dir
    servicesdir: /etc/zypp/services.d
    download.use_deltarpm: true
    # any setting in /etc/zypp/zypp.conf
```

2.18 Contributing to cloud-init

This document describes how to contribute changes to cloud-init. It assumes you have a [GitHub](#) account, and refers to your GitHub user as `GH_USER` throughout.

2.18.1 Submitting your first pull request

Summary

Before any pull request can be accepted, you must do the following:

- Sign the Canonical [contributor license agreement](#)
- Add your Github username (alphabetically) to the in-repository list that we use to track CLA signatures: [tools/.github-cla-signers](#)
- Add or update any [unit tests](#) accordingly
- Add or update any [integration tests](#) (if applicable)
- Format code (using `black` and `isort`) with `tox -e do_format`
- Ensure unit tests and linting pass using `tox`
- Submit a PR against the *main* branch of the *cloud-init* repository

The detailed instructions

Follow these steps to submit your first pull request to cloud-init:

- To contribute to cloud-init, you must sign the Canonical [contributor license agreement](#)
 - If you have already signed it as an individual, your Launchpad user will be listed in the [contributor-agreement-canonical](#) group. (Unfortunately there is no easy way to check if an organization or company you are doing work for has signed.)
 - When signing it:
 - * ensure that you fill in the GitHub username field.
 - * when prompted for ‘Project contact’ or ‘Canonical Project Manager’, enter ‘James Falcon’.
 - If your company has signed the CLA for you, please contact us to help in verifying which Launchpad/GitHub accounts are associated with the company.
 - For any questions or help with the process, please email [James Falcon](#) with the subject, “Cloud-Init CLA”
 - You also may contact user `falcojr` in the `#cloud-init` channel on the Libera IRC network.
- Configure git with your email and name for commit messages.

Your name will appear in commit messages and will also be used in changelogs or release notes. Give yourself credit!:

```
git config user.name "Your Name"
git config user.email "Your Email"
```

- Sign into your [GitHub](#) account
- Fork the upstream [repository](#) on Github and clicking on the Fork button

- Create a new remote pointing to your personal GitHub repository.

```
git clone git@github.com:GH_USER/cloud-init.git
cd cloud-init
git remote add upstream git@github.com:canonical/cloud-init.git
git push origin main
```

- Read through the cloud-init [Code Review Process](#), so you understand how your changes will end up in cloud-init's codebase.
- Submit your first cloud-init pull request, adding your Github username to the in-repository list that we use to track CLA signatures: [tools/.github-cla-signers](#)
 - See [PR #344](#) and [PR #345](#) for examples of what this pull request should look like.
 - Note that `.github-cla-signers` is sorted alphabetically.
 - (If you already have a change that you want to submit, you can also include the change to `tools/.github-cla-signers` in that pull request, there is no need for two separate PRs.)

Transferring CLA Signatures from Launchpad to Github

For existing contributors who have signed the agreement in Launchpad before the Github username field was included, we need to verify the link between your [Launchpad](#) account and your [GitHub](#) account. To enable us to do this, we ask that you create a branch with both your Launchpad and GitHub usernames against both the Launchpad and GitHub cloud-init repositories. We've added a tool (`tools/migrate-lp-user-to-github`) to the cloud-init repository to handle this migration as automatically as possible.

The cloud-init team will review the two merge proposals and verify that the CLA has been signed for the Launchpad user and record the associated GitHub account.

Note: If you are a first time contributor, you will not need to touch Launchpad to contribute to cloud-init: all new CLA signatures are handled as part of the GitHub pull request process described above.

2.18.2 Do these things for each feature or bug

- Create a new topic branch for your work:

```
git checkout -b my-topic-branch
```

- Make and commit your changes (note, you can make multiple commits, fixes, more commits.):

```
git commit
```

- Apply black and isort formatting rules with `tox`:

```
tox -e do_format
```

- Run unit tests and lint/formatting checks with `tox`:

```
tox
```

- Push your changes to your personal GitHub repository:

```
git push -u origin my-topic-branch
```

- Use your browser to create a pull request:
 - Open the branch on GitHub
 - * You can see a web view of your repository and navigate to the branch at:
`https://github.com/GH_USER/cloud-init/tree/my-topic-branch`
 - Click ‘Pull Request’
 - Fill out the pull request title, summarizing the change and a longer message indicating important details about the changes included, like

Activate the frobnicator.

The frobnicator was previously inactive and now runs by default. This may save the world some day. Then, list the bugs you fixed as footers with syntax as shown here.

The commit message should be one summary line of less than 70 characters followed by a blank line, and then one or more paragraphs wrapped at 72 characters describing the change and why it was needed.

This is the message that will be used on the commit when it is squashed and merged into main. If there is a related launchpad bug, specify it at the bottom of the commit message.

LP: *#NNNNNNN (replace with the appropriate bug reference or remove this line entirely if there is no associated bug)*

Note that the project continues to use LP: #NNNNN format for closing launchpad bugs rather than GitHub Issues.

- Click ‘Create Pull Request’

Then, a cloud-init committer will review your changes and follow up in the pull request. Look at the [Code Review Process](#) doc to understand the following steps.

Feel free to ping and/or join #cloud-init on Libera irc if you have any questions.

2.18.3 Design

This section captures design decisions that are helpful to know when hacking on cloud-init.

Python Support

Cloud-init upstream currently supports Python 3.6 and above.

Cloud-init upstream will stay compatible with a particular python version for 6 years after release. After 6 years, we will stop testing upstream changes against the unsupported version of python and may introduce breaking changes. This policy may change as needed.

The following table lists the cloud-init versions in which the minimum python version changed:

Cloud-init version	Python version
22.1	3.6+
20.3	3.5+
19.4	2.7+

Cloud Config Modules

- Any new modules should use underscores in any new config options and not hyphens (e.g. *new_option* and *not new-option*).

Tests

Submissions to cloud-init must include testing. See [Testing](#) for details on these requirements.

Type Annotations

The cloud-init codebase uses Python's annotation support for storing type annotations in the style specified by [PEP-484](#) and [PEP-526](#). Their use in the codebase is encouraged.

Feature Flags

Feature flags are used as a way to easily toggle configuration **at build time**. They are provided to accommodate feature deprecation and downstream configuration changes.

Currently used upstream values for feature flags are set in `cloudinit/features.py`. Overrides to these values (typically via quilt patch) can be placed in a file called `feature_overrides.py` in the same directory. Any value set in `feature_overrides.py` will override the original value set in `features.py`.

Each flag should include a short comment regarding the reason for the flag and intended lifetime.

Tests are required for new feature flags, and tests must verify all valid states of a flag, not just the default state.

`cloudinit.features.ALLOW_EC2_MIRRORS_ON_NON_AWS_INSTANCE_TYPES = False`

When configuring apt mirrors, if `ALLOW_EC2_MIRRORS_ON_NON_AWS_INSTANCE_TYPES` is `True` cloud-init will detect that a datasource's `availability_zone` property looks like an EC2 availability zone and set the `ec2_region` variable when generating mirror URLs; this can lead to incorrect mirrors being configured in clouds whose AZs follow EC2's naming pattern.

As of 20.3, `ALLOW_EC2_MIRRORS_ON_NON_AWS_INSTANCE_TYPES` is `False` so we no longer include `ec2_region` in mirror determination on non-AWS cloud platforms.

If the old behavior is desired, users can provide the appropriate mirrors via `apt:` directives in cloud-config.

`cloudinit.features.ERROR_ON_USER_DATA_FAILURE = True`

If there is a failure in obtaining user data (i.e., `#include` or `decompress` fails) and `ERROR_ON_USER_DATA_FAILURE` is `False`, cloud-init will log a warning and proceed. If it is `True`, cloud-init will instead raise an exception.

As of 20.3, `ERROR_ON_USER_DATA_FAILURE` is `True`.

(This flag can be removed after Focal is no longer supported.)

`cloudinit.features.EXPIRE_APPLIES_TO_HASHED_USERS = True`

If `EXPIRE_APPLIES_TO_HASHED_USERS` is `True`, then when `expire` is set `true` in `cc_set_passwords`, hashed passwords will be expired. Previous to 22.3, only non-hashed passwords were expired.

(This flag can be removed after Jammy is no longer supported.)

2.19 Module Creation

Much of cloud-init functionality is provided by *modules*. All modules follow a similar layout in order to provide consistent execution and documentation. Use the example provided here to create a new module.

2.19.1 Example

```
# This file is part of cloud-init. See LICENSE file for license information.
"""Example Module: Shows how to create a module"""

from logging import Logger

from cloudinit.cloud import Cloud
from cloudinit.config import Config
from cloudinit.config.schema import MetaSchema, get_meta_doc
from cloudinit.distros import ALL_DISTROS
from cloudinit.settings import PER_INSTANCE

MODULE_DESCRIPTION = """\
Description that will be used in module documentation.

This will likely take multiple lines.
"""

meta: MetaSchema = {
    "id": "cc_example",
    "name": "Example Module",
    "title": "Shows how to create a module",
    "description": MODULE_DESCRIPTION,
    "distros": [ALL_DISTROS],
    "frequency": PER_INSTANCE,
    "activate_by_schema_keys": ["example_key", "example_other_key"],
    "examples": [
```

(continues on next page)

(continued from previous page)

```

        "example_key: example_value",
        "example_other_key: ['value', 2]",
    ],
}

__doc__ = get_meta_doc(meta)

def handle(
    name: str, cfg: Config, cloud: Cloud, log: Logger, args: list
) -> None:
    log.debug(f"Hi from module {name}")

```

2.19.2 Guidelines

- Create a new module in the `cloudinit/config` directory with a `cc_` prefix.
- Your module must include a `handle` function. The arguments are:
 - `name`: The module name specified in the configuration
 - `cfg`: A configuration object that is the result of the merging of cloud-config configuration with any data-source provided configuration.
 - `cloud`: A cloud object that can be used to access various datasource and paths for the given distro and data provided by the various datasource instance types.
 - `log`: A logger object that can be used to log messages.
 - `args`: An argument list. This is usually empty and is only populated if the module is called independently from the command line or if the module definition in `/etc/cloud/cloud.cfg.d` has been modified to pass arguments to this module.
- If your module introduces any new cloud-config keys, you must provide a schema definition in `cloud-init-schema.json`.
- The `meta` variable must exist and be of type `MetaSchema`.
 - `id`: The module id. In most cases this will be the filename without the `.py` extension.
 - `distros`: Defines the list of supported distros. It can contain any of the values (not keys) defined in the `OSFAMILIES` map or `[ALL_DISTROS]` if there is no distro restriction.
 - `frequency`: Defines how often module runs. It must be one of:
 - * `PER_ALWAYS`: Runs on every boot.
 - * `ONCE`: Runs only on first boot.
 - * `PER_INSTANCE`: Runs once per instance. When exactly this happens is dependent on the datasource but may triggered anytime there would be a significant change to the instance metadata. An example could be an instance being moved to a different subnet.
 - `activate_by_schema_keys`: (Optional) List of cloud-config keys that will activate this module. When this list not empty, the config module will be skipped unless one of the `activate_by_schema_keys` are present in merged cloud-config instance-data.

- `examples`: Lists examples of any cloud-config keys this module reacts to. These examples will be rendered in the module reference documentation and will automatically be tested against the defined schema during testing.
- `__doc__ = get_meta_doc(meta)` is necessary to provide proper module documentation.

2.19.3 Module Execution

In order for a module to be run, it must be defined in a module run section in `/etc/cloud/cloud.cfg` or `/etc/cloud/cloud.cfg.d` on the launched instance. The three module sections are `cloud_init_modules`, `cloud_config_modules`, and `cloud_final_modules`, corresponding to the *Network*, *Config*, and *Final* boot stages respectively.

Add your module to `cloud.cfg.tpl` under the appropriate module section. Each module gets run in the order listed, so ensure your module is defined in the correct location based on dependencies. If your module has no particular dependencies or is not necessary for a later boot stage, it should be placed in the `cloud_final_modules` section before the `final-message` module.

2.20 Code Review Process

In order to manage incoming pull requests effectively, and provide timely feedback and/or acceptance this document serves as a guideline for the review process and outlines the expectations for those submitting code to the project as well as those reviewing the code. Code is reviewed for acceptance by at least one core team member (later referred to as committers), but comments and suggestions from others are encouraged and welcome.

The process is intended to provide timely and actionable feedback for any submission.

2.20.1 Asking For Help

cloud-init contributors, potential contributors, community members and users are encouraged to ask for any help that they need. If you have questions about the code review process, or at any point during the code review process, these are the available avenues:

- if you have an open Pull Request, comment on that pull request
- join the `#cloud-init` channel on the Libera IRC network and ask away
- send an email to the cloud-init mailing list, cloud-init@lists.launchpad.net

These are listed in rough order of preference, but use whichever of them you are most comfortable with.

2.20.2 Goals

This process has the following goals:

- Ensure code reviews occur in a timely fashion and provide actionable feedback if changes are desired.
- Ensure the minimization of ancillary problems to increase the efficiency for those reviewing the submitted code

2.20.3 Role Definitions

Any code review process will have (at least) two involved parties. For our purposes, these parties are referred to as **Proposer** and **Reviewer**. (We also have the **Committer** role which is a special case of the **Reviewer** role.) The terms are defined here (and the use of the singular form is not meant to imply that they refer to a single person):

Proposer

The person proposing a pull request (hereafter known as a PR).

Reviewer

A person who is reviewing a PR.

Committer

A cloud-init core developer (i.e. a person who has permission to merge PRs into **main**).

2.20.4 Prerequisites For Landing Pull Requests

Before a PR can be landed into **main**, the following conditions *must* be met:

- the CLA has been signed by the **Proposer** (or is covered by an entity-level CLA signature)
- all required status checks are passing
- at least one “Approve” review from a **Committer**
- no “Request changes” reviews from any **Committer**

The following conditions *should* be met:

- any Python functions/methods/classes have docstrings added/updated
- any changes to config module behaviour are captured in the documentation of the config module
- any Python code added has corresponding unit tests
- no “Request changes” reviews from any **Reviewer**

These conditions can be relaxed at the discretion of the **Committers** on a case-by-case basis. Generally, for accountability, this should not be the decision of a single **Committer**, and the decision should be documented in comments on the PR.

(To take a specific example, the `cc_phone_home` module had no tests at the time [PR #237](#) was submitted, so the **Proposer** was not expected to write a full set of tests for their minor modification, but they were expected to update the config module docs.)

2.20.5 Non-Committer Reviews

Reviews from non-**Committers** are *always* welcome. Please feel empowered to review PRs and leave your thoughts and comments on any submitted PRs, regardless of the **Proposer**.

Much of the below process is written in terms of the **Committers**. This is not intended to reflect that reviews should only come from that group, but acknowledges that we are ultimately responsible for maintaining the standards of the codebase. It would be entirely reasonable (and very welcome) for a **Reviewer** to only examine part of a PR, but it would not be appropriate for a **Committer** to merge a PR without full scrutiny.

2.20.6 Opening Phase

In this phase, the **Proposer** is responsible for opening a pull request and meeting the prerequisites laid out above.

If they need help understanding the prerequisites, or help meeting the prerequisites, then they can (and should!) ask for help. See the [Asking For Help](#) section above for the ways to do that.

These are the steps that comprise the opening phase:

1. The **Proposer** opens PR
2. CI runs automatically, and if

CI fails

The **Proposer** is expected to fix CI failures. If the **Proposer** doesn't understand the nature of the failures they are seeing, they should comment in the PR to request assistance, or use another way of [Asking For Help](#).

(Note that if assistance is not requested, the **Committers** will assume that the **Proposer** is working on addressing the failures themselves. If you require assistance, please do ask for help!)

CI passes

Move on to the [Review Phase](#).

2.20.7 Review Phase

In this phase, the **Proposer** and the **Reviewers** will iterate together to, hopefully, get the PR merged into the cloud-init codebase. There are three potential outcomes: merged, rejected permanently, and temporarily closed. (The first two are covered in this section; see [Inactive Pull Requests](#) for details about temporary closure.)

(In the below, when the verbs “merge” or “squash merge” are used, they should be understood to mean “squash merged using the GitHub UI”, which is the only way that changes can land in cloud-init's **main** branch.)

These are the steps that comprise the review phase:

1. **The Committers** assign a **Committer** to the PR

This **Committer** is expected to shepherd the PR to completion (and merge it, if that is the outcome reached). This means that they will perform an initial review, and monitor the PR to ensure that the **Proposer** is receiving any assistance that they require. The **Committers** will perform this assignment on a daily basis.

This assignment is intended to ensure that the **Proposer** has a clear point of contact with a cloud-init core developer, and that they get timely feedback after submitting a PR. It *is not* intended to preclude reviews from any other **Reviewers**, nor to imply that the **Committer** has ownership over the review process.

The assigned **Committer** may choose to delegate the code review of a PR to another **Reviewer** if they think that they would be better suited.

(Note that, in GitHub terms, this is setting an Assignee, not requesting a review.)

2. That **Committer** performs an initial review of the PR, resulting in one of the following:

Approve

If the submitted PR meets all of the [Prerequisites for Landing Pull Requests](#) and passes code review, then the **Committer** will squash merge immediately.

There may be circumstances where a PR should not be merged immediately. The wip label will be applied to PRs for which this is true. Only **Committers** are able to apply labels to PRs, so anyone who believes that this label should be applied to a PR should request its application in a comment on the PR.

The review process is **DONE**.

Approve (with nits)

If the **Proposer** submits their PR with “Allow edits from maintainer” enabled, and the only changes the **Committer** requests are minor “nits”, the **Committer** can push fixes for those nits and *immediately* squash merge. If the **Committer** does not wish to fix these nits but believes they should block a straight-up Approve, then their review should be “Needs Changes” instead.

A nit is understood to be something like a minor style issue or a spelling error, generally confined to a single line of code.

If a **Committer** is unsure as to whether their requested change is a nit, they should not treat it as a nit.

(If a **Proposer** wants to opt-out of this, then they should uncheck “Allow edits from maintainer” when submitting their PR.)

The review process is **DONE**.

Outright rejection

The **Committer** will close the PR, with useful messaging for the **Proposer** as to why this has happened.

This is reserved for cases where the proposed change is completely unfit for landing, and there is no reasonable path forward. This should only be used sparingly, as there are very few cases where proposals are completely unfit.

If a different approach to the same problem is planned, it should be submitted as a separate PR. The **Committer** should include this information in their message when the PR is closed.

The review process is **DONE**.

Needs Changes

The **Committer** will give the **Proposer** a clear idea of what is required for an Approve vote or, for more complex PRs, what the next steps towards an Approve vote are.

The **Proposer** will ask questions if they don’t understand, or disagree with, the **Committer**’s review comments.

Once consensus has been reached, the **Proposer** will address the review comments.

Once the review comments are addressed (as well as, potentially, in the interim), CI will run. If CI fails, the **Proposer** is expected to fix CI failures. If CI passes, the **Proposer** should indicate that the PR is ready for re-review (by @ing the assigned reviewer), effectively moving back to the start of this section.

2.20.8 Inactive Pull Requests

PRs will be temporarily closed if they have been waiting on **Proposer** action for a certain amount of time without activity. A PR will be marked as stale (with an explanatory comment) after 14 days of inactivity. It will be closed after a further 7 days of inactivity.

These closes are not considered permanent, and the closing message should reflect this for the **Proposer**. However, if a PR is reopened, it should effectively enter the *Opening phase* again, as it may need some work done to get CI passing again.

2.21 Security

2.21.1 Security Policy

The following documents the upstream cloud-init security policy.

Reporting

If a user finds a security issue, they are requested to file a [private security bug on Launchpad](#). To ensure the information stays private, change the “This bug contains information that is:” from “Public” to “Private Security” when filing.

After the bug is received, the issue is triaged within 2 working days of being reported and a response is sent to the reporter.

cloud-init-security

The cloud-init-security Launchpad team is a private, invite-only team used to discuss and coordinate security issues with the project.

Any issues disclosed to the cloud-init-security mailing list are considered embargoed and should only be discussed with other members of the cloud-init-security mailing list before the coordinated release date, unless specific exception is granted by the administrators of the mailing list. This includes disclosure of any details related to the vulnerability or the presence of a vulnerability itself. Violation of this policy may result in removal from the list for the company or individual involved.

Evaluation

If the reported bug is deemed a real security issue a CVE is assigned by the Canonical Security Team as CVE Numbering Authority (CNA).

If it is deemed a regular, non-security, issue, the reporter will be asked to follow typical bug reporting procedures.

In addition to the disclosure timeline, the core Canonical cloud-init team will enlist the expertise of the Ubuntu Security team for guidance on industry-standard disclosure practices as necessary.

If an issue specifically involves another distro or cloud vendor, additional individuals will be informed of the issue to help in evaluation.

Disclosure

Disclosure of security issues will be made with a public statement. Once the determined time for disclosure has arrived the following will occur:

- A public bug is filed/made public with vulnerability details, CVE, mitigations and where to obtain the fix
- An email is sent to the [public cloud-init mailing list](#)

The disclosure timeframe is coordinated with the reporter and members of the cloud-init-security list. This depends on a number of factors:

- The reporter might have their own disclosure timeline (e.g. Google Project Zero and many others use a 90-days after initial report OR when a fix becomes public)
- It might take time to decide upon and develop an appropriate fix
- A distros might want extra time to backport any possible fixes before the fix becomes public

- A cloud may need additional time to prepare to help customers or impliment a fix
- The issue might be deemed low priority
- May wish to align with an upcoming planned release

2.22 Debugging cloud-init

2.22.1 Overview

This topic will discuss general approaches for test and debug of cloud-init on deployed instances.

2.22.2 Boot Time Analysis - cloud-init analyze

Occasionally instances don't appear as performant as we would like and cloud-init packages a simple facility to inspect what operations took cloud-init the longest during boot and setup.

The script `/usr/bin/cloud-init` has an analyze sub-command **analyze** which parses any cloud-init.log file into formatted and sorted events. It allows for detailed analysis of the most costly cloud-init operations are to determine the long-pole in cloud-init configuration and setup. These subcommands default to reading `/var/log/cloud-init.log`.

- **analyze show** Parse and organize cloud-init.log events by stage and include each sub-stage granularity with time delta reports.

```
$ cloud-init analyze show -i my-cloud-init.log
-- Boot Record 01 --
The total time elapsed since completing an event is printed after the "@"
character.
The time the event takes is printed after the "+" character.

Starting stage: modules-config
|`->config-snap_config ran successfully @05.47700s +00.00100s
|`->config-ssh-import-id ran successfully @05.47800s +00.00200s
|`->config-locale ran successfully @05.48000s +00.00100s
...
```

- **analyze dump** Parse cloud-init.log into event records and return a list of dictionaries that can be consumed for other reporting needs.

```
$ cloud-init analyze dump -i my-cloud-init.log
[
{
  "description": "running config modules",
  "event_type": "start",
  "name": "modules-config",
  "origin": "cloudinit",
  "timestamp": 1510807493.0
},...
```

- **analyze blame** Parse cloud-init.log into event records and sort them based on highest time cost for quick assessment of areas of cloud-init that may need improvement.

```
$ cloud-init analyze blame -i my-cloud-init.log
-- Boot Record 11 --
  00.01300s (modules-final/config-scripts-per-boot)
  00.00400s (modules-final/config-final-message)
  00.00100s (modules-final/config-rightscales_userdata)
  ...
```

- **analyze boot** Make subprocess calls to the kernel in order to get relevant pre-cloud-init timestamps, such as the kernel start, kernel finish boot, and cloud-init start.

```
$ cloud-init analyze boot
-- Most Recent Boot Record --
Kernel Started at: 2019-06-13 15:59:55.809385
Kernel ended boot at: 2019-06-13 16:00:00.944740
Kernel time to boot (seconds): 5.135355
Cloud-init start: 2019-06-13 16:00:05.738396
Time between Kernel boot and Cloud-init start (seconds): 4.793656
```

Analyze quickstart - LXC

To quickly obtain a cloud-init log try using lxc on any ubuntu system:

```
$ lxc init ubuntu-daily:focal x1
$ lxc start x1
$ # Take lxc's cloud-init.log and pipe it to the analyzer
$ lxc file pull x1/var/log/cloud-init.log - | cloud-init analyze dump -i -
$ lxc file pull x1/var/log/cloud-init.log - | \
  python3 -m cloudinit.analyze dump -i -
```

Analyze quickstart - KVM

To quickly analyze a KVM a cloud-init log:

1. Download the current cloud image

```
$ wget https://cloud-images.ubuntu.com/daily/server/focal/current/focal-server-cloudimg-
  ↪ amd64.img
```

2. Create a snapshot image to preserve the original cloud-image

```
$ qemu-img create -b focal-server-cloudimg-amd64.img -f qcow2 \
  test-cloudinit.qcow2
```

3. Create a seed image with metadata using *cloud-localds*

```
$ cat > user-data <<EOF
#cloud-config
password: passw0rd
chpasswd: { expire: False }
EOF
$ cloud-localds my-seed.img user-data
```

4. Launch your modified VM

```
$ kvm -m 512 -net nic -net user -redir tcp:2222::22 \
  -drive file=test-cloudinit.qcow2,if=virtio,format=qcow2 \
  -drive file=my-seed.img,if=virtio,format=raw
```

5. Analyze the boot (blame, dump, show)

```
$ ssh -p 2222 ubuntu@localhost 'cat /var/log/cloud-init.log' | \
  cloud-init analyze blame -i -
```

2.22.3 Running single cloud config modules

This subcommand is not called by the init system. It can be called manually to load the configured datasource and run a single cloud-config module once using the cached userdata and metadata after the instance has booted. Each cloud-config module has a module FREQUENCY configured: PER_INSTANCE, PER_BOOT, PER_ONCE or PER_ALWAYS. When a module is run by cloud-init, it stores a semaphore file in `/var/lib/cloud/instance/sem/config_<module_name>.<frequency>` which marks when the module last successfully ran. Presence of this semaphore file prevents a module from running again if it has already been run. To ensure that a module is run again, the desired frequency can be overridden on the commandline:

```
$ sudo cloud-init single --name cc_ssh --frequency always
...
Generating public/private ed25519 key pair
...
```

Inspect `cloud-init.log` for output of what operations were performed as a result.

2.22.4 Stable Release Updates (SRU) testing for cloud-init

Once an Ubuntu release is stable (i.e. after it is released), updates for it must follow a special procedure called a “stable release update” (or [SRU](#)).

The cloud-init project has a specific process it follows when validating a cloud-init SRU, documented in the [CloudinitUpdates](#) wiki page.

Generally an SRU test of cloud-init performs the following:

- Install a pre-release version of cloud-init from the **-proposed** APT pocket (e.g. **bionic-proposed**)
- Upgrade cloud-init and attempt a clean run of cloud-init to assert the new version of cloud-init works properly the specific platform and Ubuntu series
- Check for tracebacks or errors in behavior

Manual SRU verification procedure

Below are steps to manually test a pre-release version of cloud-init from **-proposed**

Note: For each Ubuntu SRU, the Ubuntu Server team manually validates the new version of cloud-init on these platforms: **Amazon EC2, Azure, GCE, OpenStack, Oracle, Softlayer (IBM), LXD, KVM**

1. Launch a VM on your favorite platform, providing this cloud-config user-data and replacing `<YOUR_LAUNCHPAD_USERNAME>` with your username:

```
## template: jinja
#cloud-config
ssh_import_id: [<YOUR_LAUNCHPAD_USERNAME>]
hostname: SRU-worked-{{v1.cloud_name}}
```

2. Wait for current cloud-init to complete, replace `<YOUR_VM_IP>` with the IP address of the VM that you launched in step 1:

```
CI_VM_IP=<YOUR_VM_IP>
# Make note of the datasource cloud-init detected in --long output.
# In step 5, you will use this to confirm the same datasource is detected after upgrade.
ssh ubuntu@$CI_VM_IP -- cloud-init status --wait --long
```

3. Set up the **-proposed** pocket on your VM and upgrade to the **-proposed** cloud-init:

```
# Create a script that will add the -proposed pocket to APT's sources
# and install cloud-init from that pocket
cat > setup_proposed.sh <<EOF
#!/bin/bash
mirror=http://archive.ubuntu.com/ubuntu
echo deb $mirror $(lsb_release -sc)-proposed main | tee \
    /etc/apt/sources.list.d/proposed.list
apt-get update -q
apt-get install -qy cloud-init
EOF

scp setup_proposed.sh ubuntu@$CI_VM_IP:.
ssh ubuntu@$CI_VM_IP -- sudo bash setup_proposed.sh
```

4. Change hostname, clean cloud-init's state, and reboot to run cloud-init from scratch:

```
ssh ubuntu@$CI_VM_IP -- sudo hostname something-else
ssh ubuntu@$CI_VM_IP -- sudo cloud-init clean --logs --reboot
```

5. Validate **-proposed** cloud-init came up without error

```
# Block until cloud-init completes and verify from --long the datasource
# from step 1. Errors would show up in --long

ssh ubuntu@$CI_VM_IP -- cloud-init status --wait --long
# Make sure hostname was set properly to SRU-worked-<cloud name>
ssh ubuntu@$CI_VM_IP -- hostname
# Check for any errors or warnings in cloud-init logs.
# (This should produce no output if successful.)
ssh ubuntu@$CI_VM_IP -- grep Trace "/var/log/cloud-init"
```

6. If you encounter an error during SRU testing:

- Create a new [cloud-init bug](#) reporting the version of cloud-init affected
- Ping upstream cloud-init on Libera's [#cloud-init IRC channel](#)

2.23 Logging

Cloud-init supports both local and remote logging configurable through multiple configurations:

- Python's built-in logging configuration
- Cloud-init's event reporting system
- The cloud-init rsyslog module

2.23.1 Python Logging

Cloud-init uses the python logging module, and can accept config for this module using the standard python fileConfig format. Cloud-init looks for config for the logging module under the `logcfg` key.

Note: the logging configuration is not YAML, it is python fileConfig format, and is passed through directly to the python logging module. please use the correct syntax for a multi-line string in YAML.

By default, cloud-init uses the logging configuration provided in `/etc/cloud/cloud.cfg.d/05_logging.cfg`. The default python logging configuration writes all cloud-init events with a priority of `WARNING` or higher to console, and writes all events with a level of `DEBUG` or higher to `/var/log/cloud-init.log` and via syslog.

Python's fileConfig format consists of sections with headings in the format `[title]` and key value pairs in each section. Configuration for python logging must contain the sections `[loggers]`, `[handlers]`, and `[formatters]`, which name the entities of their respective types that will be defined. The section name for each defined logger, handler and formatter will start with its type, followed by an underscore (`_`) and the name of the entity. For example, if a logger was specified with the name `log01`, config for the logger would be in the section `[logger_log01]`.

Logger config entries contain basic logging set up. They may specify a list of handlers to send logging events to as well as the lowest priority level of events to handle. A logger named `root` must be specified and its configuration (under `[logger_root]`) must contain a level and a list of handlers. A level entry can be any of the following: `DEBUG`, `INFO`, `WARNING`, `ERROR`, `CRITICAL`, or `NOTSET`. For the `root` logger the `NOTSET` option will allow all logging events to be recorded.

Each configured handler must specify a class under the python's `logging` package namespace. A handler may specify a message formatter to use, a priority level, and arguments for the handler class. Common handlers are `StreamHandler`, which handles stream redirects (i.e. logging to `stderr`), and `FileHandler` which outputs to a log file. The logging module also supports logging over net sockets, over http, via smtp, and additional complex configurations. For full details about the handlers available for python logging, please see the documentation for [python logging handlers](#).

Log messages are formatted using the `logging.Formatter` class, which is configured using `formatter` config entities. A default format of `%(message)s` is given if no formatter configs are specified. Formatter config entities accept a format string which supports variable replacements. These may also accept a `datefmt` string which may be used to configure the timestamp used in the log messages. The format variables `%(asctime)s`, `%(levelname)s` and `%(message)s` are commonly used and represent the timestamp, the priority level of the event and the event message. For additional information on logging formatters see [python logging formatters](#).

Note: by default the format string used in the logging formatter are in python's old style `%s` form. the `str.format()` and `string.Template` styles can also be used by using `{` or `$` in place of `%` by setting the `style` parameter in `formatter` config.

A simple, but functional python logging configuration for cloud-init is below. It will log all messages of priority `DEBUG` or higher both `stderr` and `/tmp/my.log` using a `StreamHandler` and a `FileHandler`, using the default format string `%(message)s`:

```
logcfg: |
[loggers]
keys=root,cloudinit
[handlers]
keys=ch,cf
[formatters]
keys=
[logger_root]
level=DEBUG
handlers=
[logger_cloudinit]
level=DEBUG
qualname=cloudinit
handlers=ch,cf
[handler_ch]
class=StreamHandler
level=DEBUG
args=(sys.stderr,)
[handler_cf]
class=FileHandler
level=DEBUG
args=('/tmp/my.log',)
```

For additional information about configuring python's logging module, please see the documentation for [python logging config](#).

2.23.2 Command Output

Cloud-init can redirect its stdout and stderr based on config given under the output config key. The output of any commands run by cloud-init and any user or vendor scripts provided will also be included here. The output key accepts a dictionary for configuration. Output files may be specified individually for each stage (`init`, `config`, and `final`), or a single key `all` may be used to specify output for all stages.

The output for each stage may be specified as a dictionary of `output` and `error` keys, for stdout and stderr respectively, as a tuple with stdout first and stderr second, or as a single string to use for both. The strings passed to all of these keys are handled by the system shell, so any form of redirection that can be used in bash is valid, including piping cloud-init's output to `tee`, or `logger`. If only a filename is provided, cloud-init will append its output to the file as though `>>` was specified.

By default, cloud-init loads its output configuration from `/etc/cloud/cloud.cfg.d/05_logging.cfg`. The default config directs both stdout and stderr from all cloud-init stages to `/var/log/cloud-init-output.log`. The default config is given as

```
output: { all: "| tee -a /var/log/cloud-init-output.log" }
```

For a more complex example, the following configuration would output the `init` stage to `/var/log/cloud-init.out` and `/var/log/cloud-init.err`, for stdout and stderr respectively, replacing anything that was previously there. For the `config` stage, it would pipe both stdout and stderr through `tee -a /var/log/cloud-config.log`. For the `final` stage it would append the output of stdout and stderr to `/var/log/cloud-final.out` and `/var/log/cloud-final.err` respectively.

```
output:
  init:
```

(continues on next page)

(continued from previous page)

```

output: "> /var/log/cloud-init.out"
error: "> /var/log/cloud-init.err"
config: "tee -a /var/log/cloud-config.log"
final:
  - ">> /var/log/cloud-final.out"
  - "/var/log/cloud-final.err"

```

2.23.3 Event Reporting

Cloud-init contains an eventing system that allows events to be emitted to a variety of destinations.

3 configurations are available for reporting events:

- **webhook:** POST to a web server
- **log:** Write to the cloud-init log at configurable log level
- **stdout:** Print to stdout

The default configuration is to emit events to the cloud-init log file at DEBUG level.

Event reporting can be configured using the `reporting` key in cloud-config userdata.

Configuration

webhook

```

reporting:
  <user-defined name>:
    type: webhook
    endpoint: <url>
    timeout: <timeout in seconds>
    retries: <number of retries>
    consumer_key: <OAuth consumer key>
    token_key: <OAuth token key>
    token_secret: <OAuth token secret>
    consumer_secret: <OAuth consumer secret>

```

`endpoint` is the only additional required key when specifying `type: webhook`.

log

```

reporting:
  <user-defined name>:
    type: log
    level: <DEBUG|INFO|WARN|ERROR|FATAL>

```

`level` is optional and defaults to “DEBUG”.

print

```

reporting:
  <user-defined name>:
    type: print

```

Example

The follow example shows configuration for all three sources:

```
#cloud-config
reporting:
  webservice:
    type: webhook
    endpoint: "http://10.0.0.1:5555/asdf"
    timeout: 5
    retries: 3
    consumer_key: <consumer_key>
    token_key: <token_key>
    token_secret: <token_secret>
    consumer_secret: <consumer_secret>
  info_log:
    type: log
    level: WARN
  stdout:
    type: print
```

2.23.4 Rsyslog Module

Cloud-init's `cc_rsyslog` module allows for fully customizable rsyslog configuration under the `rsyslog` config key. The simplest way to use the rsyslog module is by specifying remote servers under the `remotes` key in `rsyslog` config. The `remotes` key takes a dictionary where each key represents the name of an rsyslog server and each value is the configuration for that server. The format for server config is:

- optional filter for log messages (defaults to `*.*`)
- optional leading `@` or `@@`, indicating udp and tcp respectively (defaults to `@`, for udp)
- ipv4 or ipv6 hostname or address. ipv6 addresses must be in `[::1]` format, (e.g. `@[fd00::1]:514`)
- optional port number (defaults to 514)

For example, to send logging to an rsyslog server named `log_serv` with address `10.0.4.1`, using port number 514, over udp, with all log messages enabled one could use either of the following.

With all options specified:

```
rsyslog:
  remotes:
    log_serv: " *.* @10.0.4.1:514"
```

With defaults used:

```
rsyslog:
  remotes:
    log_serv: "10.0.4.1"
```

For more information on rsyslog configuration, see [Rsyslog](#).

2.24 Directory layout

Cloud-init's directory structure is somewhat different from a regular application:

```
/var/lib/cloud/
- data/
  - instance-id
  - previous-instance-id
  - datasource
  - previous-datasource
  - previous-hostname
- handlers/
- instance
- instances/
  i-00000XYZ/
    - boot-finished
    - cloud-config.txt
    - datasource
    - handlers/
    - obj.pkl
    - scripts/
    - sem/
    - user-data.txt
    - user-data.txt.i
- scripts/
  - per-boot/
  - per-instance/
  - per-once/
- seed/
- sem/
```

/var/lib/cloud

The main directory containing the cloud-init specific subdirectories. It is typically located at `/var/lib` but there are certain configuration scenarios where this can be altered.

data/

Contains information related to instance ids, datasources and hostnames of the previous and current instance if they are different. These can be examined as needed to determine any information related to a previous boot (if applicable).

handlers/

Custom `part-handlers` code is written out here. Files that end up here are written out with in the scheme of `part-handler-XYZ` where `XYZ` is the handler number (the first handler found starts at 0).

instance

A symlink to the current `instances/` subdirectory that points to the currently active instance (which is active is dependent on the datasource loaded).

instances/

All instances that were created using this image end up with instance identifier subdirectories (and corresponding data for each instance). The currently active instance will be symlinked the `instance` symlink file defined previously.

scripts/

Scripts that are downloaded/created by the corresponding `part-handler` will end up in one of these subdirectories.

seed/

Contains seeded data files: meta-data, network-config, user-data, vendor-data

sem/

Cloud-init has a concept of a module semaphore, which basically consists of the module name and its frequency. These files are used to ensure a module is only ran *per-once*, *per-instance*, *per-always*. This folder contains semaphore *files* which are only supposed to run *per-once* (not tied to the instance id).

2.25 Analyze

The analyze subcommand was added to cloud-init in order to help analyze cloud-init boot time performance. It is loosely based on systemd-analyze where there are four subcommands:

- blame
- show
- dump
- boot

2.25.1 Usage

The analyze command requires one of the four subcommands:

```
$ cloud-init analyze blame
$ cloud-init analyze show
$ cloud-init analyze dump
$ cloud-init analyze boot
```

2.25.2 Availability

The analyze subcommand is generally available across all distributions with the exception of Gentoo and FreeBSD.

2.25.3 Subcommands

Blame

The blame action matches `systemd-analyze blame` where it prints, in descending order, the units that took the longest to run. This output is highly useful for examining where cloud-init is spending its time during execution.

```
$ cloud-init analyze blame
-- Boot Record 01 --
00.80300s (init-network/config-growpart)
00.64300s (init-network/config-resizefs)
00.62100s (init-network/config-ssh)
```

(continues on next page)

(continued from previous page)

```

00.57300s (modules-config/config-grub-dpkg)
00.40300s (init-local/search-NoCloud)
00.38200s (init-network/config-users-groups)
00.19800s (modules-config/config-apt-configure)
00.03700s (modules-final/config-keys-to-console)
00.02100s (init-network/config-update_etc_hosts)
00.02100s (init-network/check-cache)
00.00800s (modules-final/config-ssh-authkey-fingerprints)
00.00800s (init-network/consume-vendor-data)
00.00600s (modules-config/config-timezone)
00.00500s (modules-final/config-final-message)
00.00400s (init-network/consume-user-data)
00.00400s (init-network/config-mounts)
00.00400s (init-network/config-disk_setup)
00.00400s (init-network/config-bootcmd)
00.00400s (init-network/activate-datasource)
00.00300s (init-network/config-update_hostname)
00.00300s (init-network/config-set_hostname)
00.00200s (modules-final/config-snappy)
00.00200s (init-network/config-rsyslog)
00.00200s (init-network/config-ca-certs)
00.00200s (init-local/check-cache)
00.00100s (modules-final/config-scripts-vendor)
00.00100s (modules-final/config-scripts-per-once)
00.00100s (modules-final/config-salt-minion)
00.00100s (modules-final/config-rightscale_userdata)
00.00100s (modules-final/config-phone-home)
00.00100s (modules-final/config-package-update-upgrade-install)
00.00100s (modules-final/config-fan)
00.00100s (modules-config/config-ubuntu-advantage)
00.00100s (modules-config/config-ssh-import-id)
00.00100s (modules-config/config-snap)
00.00100s (modules-config/config-set-passwords)
00.00100s (modules-config/config-runcmd)
00.00100s (modules-config/config-locale)
00.00100s (modules-config/config-byobu)
00.00100s (modules-config/config-apt-pipelining)
00.00100s (init-network/config-write-files)
00.00100s (init-network/config-seed_random)
00.00100s (init-network/config-migrator)
00.00000s (modules-final/config-ubuntu-drivers)
00.00000s (modules-final/config-scripts-user)
00.00000s (modules-final/config-scripts-per-instance)
00.00000s (modules-final/config-scripts-per-boot)
00.00000s (modules-final/config-puppet)
00.00000s (modules-final/config-power-state-change)
00.00000s (modules-final/config-mcollective)
00.00000s (modules-final/config-lxd)
00.00000s (modules-final/config-landscape)
00.00000s (modules-final/config-chef)
00.00000s (modules-config/config-snap_config)
00.00000s (modules-config/config-ntp)

```

(continues on next page)

(continued from previous page)

```
00.000000s (modules-config/config-disable-ec2-metadata)
00.000000s (init-network/setup-datasource)
```

```
1 boot records analyzed
```

Show

The `show` action is similar to `systemd-analyze critical-chain` which prints a list of units, the time they started and how long they took. Cloud-init has four stages and within each stage a number of modules may run depending on configuration. `cloudinit-analyze show` will, for each boot, print this information and a summary total time, per boot.

The following is an abbreviated example of the `show` output:

```
$ cloud-init analyze show
-- Boot Record 01 --
The total time elapsed since completing an event is printed after the "@" character.
The time the event takes is printed after the "+" character.

Starting stage: init-local
|`->no cache found @00.01700s +00.00200s
|`->found local data from DataSourceNoCloud @00.11000s +00.40300s
Finished stage: (init-local) 00.94200 seconds

Starting stage: init-network
|`->restored from cache with run check: DataSourceNoCloud [seed=/dev/sr0][dsmode=net]
↪@04.79500s +00.02100s
|`->setting up datasource @04.88900s +00.00000s
|`->reading and applying user-data @04.90100s +00.00400s
|`->reading and applying vendor-data @04.90500s +00.00800s
|`->activating datasource @04.95200s +00.00400s
Finished stage: (init-network) 02.72100 seconds

Starting stage: modules-config
|`->config-snap ran successfully @15.43100s +00.00100s
...
|`->config-runcmd ran successfully @16.22300s +00.00100s
|`->config-byobu ran successfully @16.23400s +00.00100s
Finished stage: (modules-config) 00.83500 seconds

Starting stage: modules-final
|`->config-snappy ran successfully @16.87400s +00.00200s
|`->config-package-update-upgrade-install ran successfully @16.87600s +00.00100s
...
|`->config-final-message ran successfully @16.93700s +00.00500s
|`->config-power-state-change ran successfully @16.94300s +00.00000s
Finished stage: (modules-final) 00.10300 seconds

Total Time: 4.60100 seconds

1 boot records analyzed
```

If additional boot records are detected then they are printed out from oldest to newest.

Dump

The `dump` action simply dumps the cloud-init logs that the analyze module is performing the analysis on and returns a list of dictionaries that can be consumed for other reporting needs. Each element in the list is a boot entry.

```
$ cloud-init analyze dump
[
{
  "description": "starting search for local datasources",
  "event_type": "start",
  "name": "init-local",
  "origin": "cloudinit",
  "timestamp": 1567057578.037
},
{
  "description": "attempting to read from cache [check]",
  "event_type": "start",
  "name": "init-local/check-cache",
  "origin": "cloudinit",
  "timestamp": 1567057578.054
},
{
  "description": "no cache found",
  "event_type": "finish",
  "name": "init-local/check-cache",
  "origin": "cloudinit",
  "result": "SUCCESS",
  "timestamp": 1567057578.056
},
{
  "description": "searching for local data from DataSourceNoCloud",
  "event_type": "start",
  "name": "init-local/search-NoCloud",
  "origin": "cloudinit",
  "timestamp": 1567057578.147
},
{
  "description": "found local data from DataSourceNoCloud",
  "event_type": "finish",
  "name": "init-local/search-NoCloud",
  "origin": "cloudinit",
  "result": "SUCCESS",
  "timestamp": 1567057578.55
},
{
  "description": "searching for local datasources",
  "event_type": "finish",
  "name": "init-local",
  "origin": "cloudinit",
  "result": "SUCCESS",
  "timestamp": 1567057578.979
}
```

(continues on next page)

(continued from previous page)

```

},
{
  "description": "searching for network datasources",
  "event_type": "start",
  "name": "init-network",
  "origin": "cloudinit",
  "timestamp": 1567057582.814
},
{
  "description": "attempting to read from cache [trust]",
  "event_type": "start",
  "name": "init-network/check-cache",
  "origin": "cloudinit",
  "timestamp": 1567057582.832
},
...
{
  "description": "config-power-state-change ran successfully",
  "event_type": "finish",
  "name": "modules-final/config-power-state-change",
  "origin": "cloudinit",
  "result": "SUCCESS",
  "timestamp": 1567057594.98
},
{
  "description": "running modules for final",
  "event_type": "finish",
  "name": "modules-final",
  "origin": "cloudinit",
  "result": "SUCCESS",
  "timestamp": 1567057594.982
}
]

```

Boot

The boot action prints out kernel related timestamps that are not included in any of the cloud-init logs. There are three different timestamps that are presented to the user:

- kernel start
- kernel finish boot
- cloud-init start

This was added for additional clarity into the boot process that cloud-init does not have control over, to aid in debugging of performance issues related to cloud-init startup, and tracking regression.

```

$ cloud-init analyze boot
-- Most Recent Boot Record --
  Kernel Started at: 2019-08-29 01:35:37.753790
  Kernel ended boot at: 2019-08-29 01:35:38.807407
  Kernel time to boot (seconds): 1.053617000579834

```

(continues on next page)

(continued from previous page)

```
Cloud-init activated by systemd at: 2019-08-29 01:35:43.992460
Time between Kernel end boot and Cloud-init activation (seconds): 5.185053110122681
Cloud-init start: 2019-08-29 08:35:45.867000
successful
```

Timestamp Gathering

The following boot related timestamps are gathered on demand when cloud-init analyze boot runs:

- Kernel startup gathered from system uptime
- Kernel finishes initialization from systemd `UserSpaceMonotonicTimestamp` property
- Cloud-init activation from the property `InactiveExitTimestamp` of the cloud-init local systemd unit

In order to gather the necessary timestamps using systemd, running the commands below will gather the `UserspaceTimestamp` and `InactiveExitTimestamp`:

```
$ systemctl show -p UserspaceTimestampMonotonic
UserspaceTimestampMonotonic=989279
$ systemctl show cloud-init-local -p InactiveExitTimestampMonotonic
InactiveExitTimestampMonotonic=4493126
```

The `UserspaceTimestamp` tracks when the init system starts, which is used as an indicator of kernel finishing initialization. The `InactiveExitTimestamp` tracks when a particular systemd unit transitions from the Inactive to Active state, which can be used to mark the beginning of systemd's activation of cloud-init.

Currently this only works for distros that use systemd as the init process. We will be expanding support for other distros in the future and this document will be updated accordingly.

If systemd is not present on the system, `dmesg` is used to attempt to find an event that logs the beginning of the init system. However, with this method only the first two timestamps are able to be found; `dmesg` does not monitor userspace processes, so no cloud-init start timestamps are emitted like when using systemd.

2.26 Docs

These docs are hosted on Read the Docs. The following will explain how to contribute to and build these docs locally.

The documentation is primarily written in reStructuredText.

2.26.1 Building

There is a makefile target to build the documentation for you:

```
$ tox -e doc
```

This will do two things:

- Build the documentation using sphinx
- Run doc8 against the documentation source code

Once build the HTML files will be viewable in `doc/rtd_html`. Use your web browser to open `index.html` to view and navigate the site.

2.26.2 Style Guide

Headings

The headings used across the documentation use the following hierarchy:

- *****: used once atop of a new page
- =====: each sections on the page
- -----: subsections
- ^^^^^: sub-subsections
- """"": paragraphs

The top level header ##### is reserved for the first page.

If under and overline are used, their length must be identical. The length of the underline must be at least as long as the title itself

Line Length

Please keep the line lengths to a maximum of **79** characters. This ensures that the pages and tables do not get too wide that side scrolling is required.

Header

Adding a link at the top of the page allows for the page to be referenced by other pages. For example for the FAQ page this would be:

`.. _faq:`

Vertical Whitespace

One newline between each section helps ensure readability of the documentation source code.

Common Words

There are some common words that should follow specific usage:

- `cloud-init`: always lower case with a hyphen, unless starting a sentence in which case only the 'C' is capitalized (e.g. `Cloud-init`).
- `metadata`: one word
- `user data`: two words, not to be combined
- `vendor data`: like user data, it is two words

2.27 Testing

cloud-init has both unit tests and integration tests. Unit tests can be found at `tests/unittests`. Integration tests can be found at `tests/integration_tests`. Documentation specifically for integration tests can be found on the [Integration Testing](#) page, but the guidelines specified below apply to both types of tests.

cloud-init uses `pytest` to run its tests, and has tests written both as `unittest.TestCase` sub-classes and as un-subclassed `pytest` tests.

2.27.1 Guidelines

The following guidelines should be followed.

Test Layout

- For ease of organisation and greater accessibility for developers not familiar with `pytest`, all cloud-init unit tests must be contained within test classes
 - Put another way, module-level test functions should not be used
- As all tests are contained within classes, it is acceptable to mix `TestCase` test classes and `pytest` test classes within the same test file
 - These can be easily distinguished by their definition: `pytest` classes will not use inheritance at all (e.g. `TestGetPackageMirrorInfo`), whereas `TestCase` classes will subclass (indirectly) from `TestCase` (e.g. `TestPrependBaseCommands`)
- Unit tests and integration tests are located under `cloud-init/tests`
 - For consistency, unit test files should have a matching name and directory location under `tests/unittests`
 - For example: the expected test file for code in `cloudinit/path/to/file.py` is `tests/unittests/path/to/test_file.py`

pytest Tests

- `pytest` test classes should use `pytest fixtures` to share functionality instead of inheritance
- `pytest` tests should use bare `assert` statements, to take advantage of `pytest`'s `assertion introspection`

pytest Version Gotchas

As we still support Ubuntu 18.04 (Bionic Beaver), we can only use `pytest` features that are available in v3.3.2. This is an inexhaustive list of ways in which this may catch you out:

- Only the following built-in fixtures are available¹:
 - `cache`
 - `capfd`
 - `capfdbinary`

¹ This list of fixtures (with markup) can be reproduced by running:

```
python3 -m pytest --fixtures -q | grep "^[^ -]" | grep -v 'no tests ran in' | sort | sed 's/ \[session scope\
↩️]//g;s/.*/*`'\`/g'
```

in an ubuntu lxd container with python3-pytest installed.

- caplog
- capsys
- capsysbinary
- doctest_namespace
- monkeypatch
- pytestconfig
- record_xml_property
- recwarn
- tmpdir_factory
- tmpdir

Mocking and Assertions

- Variables/parameter names for `Mock` or `MagicMock` instances should start with `m_` to clearly distinguish them from non-mock variables
 - For example, `m_readurl` (which would be a mock for `readurl`)
- The `assert_*` methods that are available on `Mock` and `MagicMock` objects should be avoided, as typos in these method names may not raise `AttributeError` (and so can cause tests to silently pass). An important exception: if a `Mock` is `autospecced` then misspelled assertion methods *will* raise an `AttributeError`, so these assertion methods may be used on `autospecced` `Mock` objects.

For non-`autospecced` `Mock`s, these substitutions can be used (`m` is assumed to be a `Mock`):

- `m.assert_any_call(*args, **kwargs) => assert mock.call(*args, **kwargs) in m.call_args_list`
 - `m.assert_called() => assert 0 != m.call_count`
 - `m.assert_called_once() => assert 1 == m.call_count`
 - `m.assert_called_once_with(*args, **kwargs) => assert [mock.call(*args, **kwargs)] == m.call_args_list`
 - `m.assert_called_with(*args, **kwargs) => assert mock.call(*args, **kwargs) == m.call_args_list[-1]`
 - `m.assert_has_calls(call_list, any_order=True) => for call in call_list: assert call in m.call_args_list`
 - * `m.assert_has_calls(...)` and `m.assert_has_calls(..., any_order=False)` are not easily replicated in a single statement, so their use when appropriate is acceptable.
 - `m.assert_not_called() => assert 0 == m.call_count`
- When there are multiple patch calls in a test file for the module it is testing, it may be desirable to capture the shared string prefix for these patch calls in a module-level variable. If used, such variables should be named `M_PATH` or, for datasource tests, `DS_PATH`.

Test Argument Ordering

- Test arguments should be ordered as follows:
 - `mock.patch` arguments. When used as a decorator, `mock.patch` partially applies its generated `Mock` object as the first argument, so these arguments must go first.
 - `pytest.mark.parametrize` arguments, in the order specified to the `parametrize` decorator. These arguments are also provided by a decorator, so it's natural that they sit next to the `mock.patch` arguments.
 - Fixture arguments, alphabetically. These are not provided by a decorator, so they are last, and their order has no defined meaning, so we default to alphabetical.
- It follows from this ordering of test arguments (so that we retain the property that arguments left-to-right correspond to decorators bottom-to-top) that test decorators should be ordered as follows:
 - `pytest.mark.parametrize`
 - `mock.patch`

2.28 Integration Testing

2.28.1 Overview

Integration tests are written using `pytest` and are located at `tests/integration_tests`. General design principles laid out in [Testing](#) should be followed for integration tests.

Setup is accomplished via a set of fixtures located in `tests/integration_tests/conftest.py`.

2.28.2 Test Definition

Tests are defined like any other `pytest` test. The `user_data` mark can be used to supply the cloud-config user data. Platform specific marks can be used to limit tests to particular platforms. The client fixture can be used to interact with the launched test instance.

See [Examples](#) section for examples.

2.28.3 Test Execution

Test execution happens via `pytest`. A `tox` definition exists to run integration tests. To run all integration tests, you would run:

```
$ tox -e integration-tests
```

`Pytest` arguments may also be passed. For example:

```
$ tox -e integration-tests tests/integration_tests/modules/test_combined.py
```

2.28.4 Configuration

All possible configuration values are defined in `tests/integration_tests/integration_settings.py`. Defaults can be overridden by supplying values in `tests/integration_tests/user_settings.py` or by providing an environment variable of the same name prepended with `CLOUD_INIT_`. For example, to set the `PLATFORM` setting:

```
CLOUD_INIT_PLATFORM='ec2' pytest tests/integration_tests/
```

2.28.5 Cloud Interaction

Cloud interaction happens via the `pycloudlib` library. In order to run integration tests, `pycloudlib` must first be [configured](#).

For a minimal setup using LXD, write the following to `~/.config/pycloudlib.toml`:

```
[lxd]
```

2.28.6 Image Selection

Each integration testing run uses a single image as its basis. This image is configured using the `OS_IMAGE` variable; see [Configuration](#) for details of how configuration works.

`OS_IMAGE` can take two types of value: an Ubuntu series name (e.g. “focal”), or an image specification. If an Ubuntu series name is given, then the most recent image for that series on the target cloud will be used. For other use cases, an image specification is used.

In its simplest form, an image specification can simply be a cloud’s image ID (e.g. “ami-deadbeef”, “ubuntu:focal”). In this case, the image so-identified will be used as the basis for this testing run.

This has a drawback, however: as we do not know what OS or release is within the image, the integration testing framework will run *all* tests against the image in question. If it’s a RHEL8 image, then we would expect Ubuntu-specific tests to fail (and vice versa).

To address this, a full image specification can be given. This is of the form: `<image_id>[:<os>[:<release>]]` where `image_id` is a cloud’s image ID, `os` is the OS name, and `release` is the OS release name. So, for example, Ubuntu 18.04 (Bionic Beaver) on LXD is `ubuntu:bionic::ubuntu::bionic` or RHEL 8 on Amazon is `ami-justanexample::rhel::8`. When a full specification is given, only tests which are intended for use on that OS and release will be executed.

2.28.7 Image Setup

Image setup occurs once when a test session begins and is implemented via fixture. Image setup roughly follows these steps:

- Launch an instance on the specified test platform
- Install the version of cloud-init under test
- Run `cloud-init clean` on the instance so subsequent boots resemble out of the box behavior
- Take a snapshot of the instance to be used as a new image from which new instances can be launched

2.28.8 Test Setup

Test setup occurs between image setup and test execution. Test setup is implemented via one of the `client` fixtures. When a client fixture is used, a test instance from which to run tests is launched prior to test execution and torn down after.

2.28.9 Continuous Integration

A subset of the integration tests are run when a pull request is submitted on Github. The tests run on these continuous integration (CI) runs are given a pytest mark:

```
@pytest.mark.ci
```

Most new tests should *not* use this mark, so be aware that having a successful CI run does not necessarily mean that your test passed successfully.

2.28.10 Fixtures

Integration tests rely heavily on fixtures to do initial test setup. One or more of these fixtures will be used in almost every integration test.

Details such as the cloud platform or initial image to use are determined via what is specified in the [Configuration](#).

client

The `client` fixture should be used for most test cases. It ensures:

- All setup performed by [session_cloud](#) and [setup_image](#)
- [Pytest marks](#) used during instance creation are obtained and applied
- The test instance is launched
- Test failure status is determined after test execution
- Logs are collected (if configured) after test execution
- The test instance is torn down after test execution

`module_client` and `class_client` fixtures also exist for the purpose of running multiple tests against a single launched instance. They provide the exact same functionality as `client`, but are scoped to the module or class respectively.

session_cloud

The `session_cloud` session-scoped fixture will provide an [IntegrationCloud](#) instance for the currently configured cloud. The fixture also ensures that any custom cloud session cleanup is performed.

setup_image

The `setup_image` session-scope fixture will create a new image to launch all further cloud instances during this test run. It ensures:

- A cloud instance is launched on the configured platform
- The version of cloud-init under test is installed on the instance
- `cloud-init clean --logs` is run on the instance
- A snapshot of the instance is taken to be used as the basis for future instance launches
- The originally launched instance is torn down
- The custom created image is torn down after all tests finish

Examples

A simple test case using the `client` fixture:

```
USER_DATA = """\
#cloud-config
bootcmd:
- echo 'hello!' > /var/tmp/hello.txt
"""

@pytest.mark.user_data(USER_DATA)
def test_bootcmd(client):
    log = client.read_from_file("/var/log/cloud-init.log")
    assert "Shellified 1 commands." in log
    assert client.execute('cat /var/tmp/hello.txt').strip() == "hello!"
```

Customizing the launch arguments before launching an instance manually:

```
def test_launch(session_cloud: IntegrationCloud, setup_image):
    with session_cloud.launch(launch_kwargs={"wait": False}) as client:
        client.instance.wait()
        assert client.execute("echo hello world").strip() == "hello world"
```


PYTHON MODULE INDEX

C

- cloudinit.config.cc_ansible, 149
- cloudinit.config.cc_apk_configure, 152
- cloudinit.config.cc_apt_configure, 153
- cloudinit.config.cc_apt_pipelining, 158
- cloudinit.config.cc_bootcmd, 158
- cloudinit.config.cc_byobu, 159
- cloudinit.config.cc_ca_certs, 159
- cloudinit.config.cc_chef, 160
- cloudinit.config.cc_disable_ec2_metadata, 163
- cloudinit.config.cc_disk_setup, 163
- cloudinit.config.cc_fan, 165
- cloudinit.config.cc_final_message, 166
- cloudinit.config.cc_growpart, 166
- cloudinit.config.cc_grub_dpkg, 168
- cloudinit.config.cc_install_hotplug, 168
- cloudinit.config.cc_keyboard, 169
- cloudinit.config.cc_keys_to_console, 170
- cloudinit.config.cc_landscape, 170
- cloudinit.config.cc_locale, 172
- cloudinit.config.cc_lxd, 172
- cloudinit.config.cc_mcollective, 176
- cloudinit.config.cc_migrator, 177
- cloudinit.config.cc_mounts, 177
- cloudinit.config.cc_ntp, 179
- cloudinit.config.cc_package_update_upgrade_install, 180
- cloudinit.config.cc_phone_home, 181
- cloudinit.config.cc_power_state_change, 182
- cloudinit.config.cc_puppet, 183
- cloudinit.config.cc_resizefs, 186
- cloudinit.config.cc_resolv_conf, 186
- cloudinit.config.cc_rh_subscription, 187
- cloudinit.config.cc_rightscale_userdata, 189
- cloudinit.config.cc_rsyslog, 189
- cloudinit.config.cc_runcmd, 191
- cloudinit.config.cc_salt_minion, 192
- cloudinit.config.cc_scripts_per_boot, 193
- cloudinit.config.cc_scripts_per_instance, 193
- cloudinit.config.cc_scripts_per_once, 193
- cloudinit.config.cc_scripts_user, 193
- cloudinit.config.cc_scripts_vendor, 194
- cloudinit.config.cc_seed_random, 194
- cloudinit.config.cc_set_hostname, 195
- cloudinit.config.cc_set_passwords, 196
- cloudinit.config.cc_snap, 198
- cloudinit.config.cc_spacewalk, 199
- cloudinit.config.cc_ssh, 200
- cloudinit.config.cc_ssh_authkey_fingerprints, 203
- cloudinit.config.cc_ssh_import_id, 203
- cloudinit.config.cc_timezone, 204
- cloudinit.config.cc_ubuntu_advantage, 204
- cloudinit.config.cc_ubuntu_autoinstall, 206
- cloudinit.config.cc_ubuntu_drivers, 207
- cloudinit.config.cc_update_etc_hosts, 208
- cloudinit.config.cc_update_hostname, 209
- cloudinit.config.cc_users_groups, 210
- cloudinit.config.cc_wireguard, 213
- cloudinit.config.cc_write_files, 215
- cloudinit.config.cc_yum_add_repo, 217
- cloudinit.config.cc_zypper_add_repo, 218
- cloudinit.features, 223

A

ALLOW_EC2_MIRRORS_ON_NON_AWS_INSTANCE_TYPES
(in module *cloudinit.features*), 223

C

cloudinit.config.cc_ansible
module, 149
cloudinit.config.cc_apk_configure
module, 152
cloudinit.config.cc_apt_configure
module, 153
cloudinit.config.cc_apt_pipelining
module, 158
cloudinit.config.cc_bootcmd
module, 158
cloudinit.config.cc_byobu
module, 159
cloudinit.config.cc_ca_certs
module, 159
cloudinit.config.cc_chef
module, 160
cloudinit.config.cc_disable_ec2_metadata
module, 163
cloudinit.config.cc_disk_setup
module, 163
cloudinit.config.cc_fan
module, 165
cloudinit.config.cc_final_message
module, 166
cloudinit.config.cc_growpart
module, 166
cloudinit.config.cc_grub_dpkg
module, 168
cloudinit.config.cc_install_hotplug
module, 168
cloudinit.config.cc_keyboard
module, 169
cloudinit.config.cc_keys_to_console
module, 170
cloudinit.config.cc_landscape
module, 170
cloudinit.config.cc_locale

module, 172
cloudinit.config.cc_lxd
module, 172
cloudinit.config.cc_mcollective
module, 176
cloudinit.config.cc_migrator
module, 177
cloudinit.config.cc_mounts
module, 177
cloudinit.config.cc_ntp
module, 179
cloudinit.config.cc_package_update_upgrade_install
module, 180
cloudinit.config.cc_phone_home
module, 181
cloudinit.config.cc_power_state_change
module, 182
cloudinit.config.cc_puppet
module, 183
cloudinit.config.cc_resizefs
module, 186
cloudinit.config.cc_resolv_conf
module, 186
cloudinit.config.cc_rh_subscription
module, 187
cloudinit.config.cc_rightscales_userdata
module, 189
cloudinit.config.cc_rsyslog
module, 189
cloudinit.config.cc_runcmd
module, 191
cloudinit.config.cc_salt_minion
module, 192
cloudinit.config.cc_scripts_per_boot
module, 193
cloudinit.config.cc_scripts_per_instance
module, 193
cloudinit.config.cc_scripts_per_once
module, 193
cloudinit.config.cc_scripts_user
module, 193
cloudinit.config.cc_scripts_vendor

- module, 194
- cloudinit.config.cc_seed_random
 - module, 194
- cloudinit.config.cc_set_hostname
 - module, 195
- cloudinit.config.cc_set_passwords
 - module, 196
- cloudinit.config.cc_snap
 - module, 198
- cloudinit.config.cc_spacewalk
 - module, 199
- cloudinit.config.cc_ssh
 - module, 200
- cloudinit.config.cc_ssh_authkey_fingerprints
 - module, 203
- cloudinit.config.cc_ssh_import_id
 - module, 203
- cloudinit.config.cc_timezone
 - module, 204
- cloudinit.config.cc_ubuntu_advantage
 - module, 204
- cloudinit.config.cc_ubuntu_autoinstall
 - module, 206
- cloudinit.config.cc_ubuntu_drivers
 - module, 207
- cloudinit.config.cc_update_etc_hosts
 - module, 208
- cloudinit.config.cc_update_hostname
 - module, 209
- cloudinit.config.cc_users_groups
 - module, 210
- cloudinit.config.cc_wireguard
 - module, 213
- cloudinit.config.cc_write_files
 - module, 215
- cloudinit.config.cc_yum_add_repo
 - module, 217
- cloudinit.config.cc_zypper_add_repo
 - module, 218
- cloudinit.features
 - module, 223

E

`ERROR_ON_USER_DATA_FAILURE` (in module *cloudinit.features*), 224

`EXPIRE_APPLIES_TO_HASHED_USERS` (in module *cloudinit.features*), 224

M

module

- cloudinit.config.cc_ansible, 149
- cloudinit.config.cc_apk_configure, 152
- cloudinit.config.cc_apt_configure, 153
- cloudinit.config.cc_apt_pipelining, 158

- cloudinit.config.cc_bootcmd, 158
- cloudinit.config.cc_byobu, 159
- cloudinit.config.cc_ca_certs, 159
- cloudinit.config.cc_chef, 160
- cloudinit.config.cc_disable_ec2_metadata, 163
- cloudinit.config.cc_disk_setup, 163
- cloudinit.config.cc_fan, 165
- cloudinit.config.cc_final_message, 166
- cloudinit.config.cc_growpart, 166
- cloudinit.config.cc_grub_dpkg, 168
- cloudinit.config.cc_install_hotplug, 168
- cloudinit.config.cc_keyboard, 169
- cloudinit.config.cc_keys_to_console, 170
- cloudinit.config.cc_landscape, 170
- cloudinit.config.cc_locale, 172
- cloudinit.config.cc_lxd, 172
- cloudinit.config.cc_mcollective, 176
- cloudinit.config.cc_migrator, 177
- cloudinit.config.cc_mounts, 177
- cloudinit.config.cc_ntp, 179
- cloudinit.config.cc_package_update_upgrade_install, 180
- cloudinit.config.cc_phone_home, 181
- cloudinit.config.cc_power_state_change, 182
- cloudinit.config.cc_puppet, 183
- cloudinit.config.cc_resizefs, 186
- cloudinit.config.cc_resolv_conf, 186
- cloudinit.config.cc_rh_subscription, 187
- cloudinit.config.cc_rightscale_userdata, 189
- cloudinit.config.cc_rsyslog, 189
- cloudinit.config.cc_runcmd, 191
- cloudinit.config.cc_salt_minion, 192
- cloudinit.config.cc_scripts_per_boot, 193
- cloudinit.config.cc_scripts_per_instance, 193
- cloudinit.config.cc_scripts_per_once, 193
- cloudinit.config.cc_scripts_user, 193
- cloudinit.config.cc_scripts_vendor, 194
- cloudinit.config.cc_seed_random, 194
- cloudinit.config.cc_set_hostname, 195
- cloudinit.config.cc_set_passwords, 196
- cloudinit.config.cc_snap, 198
- cloudinit.config.cc_spacewalk, 199
- cloudinit.config.cc_ssh, 200
- cloudinit.config.cc_ssh_authkey_fingerprints, 203
- cloudinit.config.cc_ssh_import_id, 203
- cloudinit.config.cc_timezone, 204
- cloudinit.config.cc_ubuntu_advantage, 204
- cloudinit.config.cc_ubuntu_autoinstall, 206

cloudinit.config.cc_ubuntu_drivers, [207](#)
cloudinit.config.cc_update_etc_hosts, [208](#)
cloudinit.config.cc_update_hostname, [209](#)
cloudinit.config.cc_users_groups, [210](#)
cloudinit.config.cc_wireguard, [213](#)
cloudinit.config.cc_write_files, [215](#)
cloudinit.config.cc_yum_add_repo, [217](#)
cloudinit.config.cc_zypper_add_repo, [218](#)
cloudinit.features, [223](#)